

IBM Informix
Version 11.50

IBM Informix SNMP Subagent Guide



IBM Informix
Version 11.50

IBM Informix SNMP Subagent Guide



Note:

Before using this information and the product it supports, read the information in "Notices" on page B-1.

This document contains proprietary information of IBM. It is provided under a license agreement and is protected by copyright law. The information contained in this publication does not include any product warranties, and any statements provided in this manual should not be interpreted as such.

When you send information to IBM, you grant IBM a nonexclusive right to use or distribute the information in any way it believes appropriate without incurring any obligation to you.

© Copyright IBM Corporation 1996, 2010.

US Government Users Restricted Rights – Use, duplication or disclosure restricted by GSA ADP Schedule Contract with IBM Corp.

Contents

Introduction	v
About this publication	v
What's New in SNMP for Informix, Version 11.50	v
Types of users	vi
Software dependencies.	vi
Assumptions about your locale	vi
Demonstration databases	vi
Example Code Conventions	vii
Additional Documentation	vii
Compliance with Industry Standards.	vii
Syntax Diagrams	viii
How to Read a Command-Line Syntax Diagram	ix
Keywords and Punctuation	x
Identifiers and Names	x
How to Provide Documentation Feedback	xi
 Chapter 1. SNMP concepts	 1-1
What the SNMP is.	1-1
Purpose of the SNMP.	1-1
SNMP architecture.	1-1
SNMP network managers	1-2
Master agents	1-4
Subagents.	1-4
Managed components.	1-4
MIBs	1-5
 Chapter 2. IBM Informix implementation of SNMP	 2-1
Components of the Informix implementation	2-1
Purpose of IBM Informix SNMP	2-2
Event notification	2-2
Data requests	2-2
Traps	2-3
Information that OnSNMP provides	2-3
SNMP standard.	2-3
SNMP architecture.	2-4
IBM Informix SNMP architecture on UNIX	2-4
IBM Informix SNMP architecture on Windows	2-4
Using SNMP on UNIX or Linux	2-5
The runsnmp.ksh script	2-6
UNIX master agents	2-6
UNIX subagent	2-9
UNIX server discovery process	2-9
Using SNMP on Windows.	2-11
Windows Master Agent.	2-11
Windows subagent	2-11
Windows server discovery process	2-13
GLS and SNMP	2-14
MIBs	2-14
Application MIB	2-14
RDBMS MIB	2-15
Informix private MIB	2-15
Online MIB.	2-16
MIB objects.	2-16
Table indexing.	2-17
Numeric index values	2-17

Alphabetical index values	2-17
Refresh control value	2-18
Files installed for SNMP	2-18
Files installed on UNIX or Linux	2-18
Files installed on Windows	2-19

Chapter 3. MIB reference. 3-1

MIBs that OnSNMP uses.	3-1
Application MIB	3-2
applTable	3-2
RDBMS MIB.	3-4
rdbmsDbInfoTable	3-4
rdbmsDbLimitedResourceTable	3-4
rdbmsDbParamTable	3-5
rdbmsDbTable	3-5
rdbmsRelTable	3-5
rdbmsSrvInfoTable.	3-6
rdbmsSrvLimitedResourceTable	3-6
rdbmsSrvParamTable	3-7
rdbmsSrvTable	3-8
rdbmsTraps	3-8
Online MIB in the Informix private MIB	3-9
onActiveBarTable	3-9
onActiveTableTable	3-9
onBarTable	3-10
onChunkTable	3-11
onDatabaseTable	3-12
onDbospaceTable	3-13
onErQueueTable	3-14
onErSiteTable	3-14
onFragmentTable	3-16
onLockTable	3-17
onLogicalLogTable	3-18
onPhysicalLogTable	3-18
onServerTable	3-19
onSessionTable.	3-20
onSqlHostTable	3-22
onTableTable	3-23

Appendix. Accessibility A-1

Accessibility features for IBM Informix.	A-1
Accessibility Features	A-1
Keyboard Navigation	A-1
Related Accessibility Information.	A-1
IBM and Accessibility	A-1
Dotted Decimal Syntax Diagrams	A-1

Notices B-1

Trademarks	B-3
----------------------	-----

Index X-1

Introduction

About this publication	v
What's New in SNMP for Informix, Version 11.50	v
Types of users	vi
Software dependencies.	vi
Assumptions about your locale	vi
Demonstration databases	vi
Example Code Conventions	vii
Additional Documentation	vii
Compliance with Industry Standards.	vii
Syntax Diagrams	viii
How to Read a Command-Line Syntax Diagram	ix
Keywords and Punctuation	x
Identifiers and Names	x
How to Provide Documentation Feedback	xi

About this publication

This publication describes the Simple Network Management Protocol (SNMP) and the software that you need to use SNMP to monitor and manage Informix® database servers and databases.

What's New in SNMP for Informix, Version 11.50

This publication includes information about new features and changes in existing functionality.

The following changes and enhancements are relevant to this publication. For a complete list of what's new in this release, see the release notes or the information center.

Table 1. What's New in IBM Informix SNMP Subagent Guide

Overview	Reference
New editions and product names: Dynamic Server editions were withdrawn and new Informix editions are available. Some products were also renamed. The publications in the Informix library pertain to the following products: <ul style="list-style-type: none">• IBM® Informix database server, formerly known as IBM Informix Dynamic Server (IDS)• IBM OpenAdmin Tool for Informix, formerly known as OpenAdmin Tool for Informix Dynamic Server (IDS)• IBM Informix SQL Warehousing Tool, formerly known as Informix Warehouse Feature	For more information about the Informix product family, go to http://www.ibm.com/software/data/informix/ .

Types of users

This manual is written for the following users:

- Database server administrators
- Backup operators
- Performance engineers

This manual assumes that you have the following background:

- A working knowledge of your computer, your operating system, and the utilities that your operating system provides
- Some experience with database server administration, operating-system administration, or network administration

Software dependencies

This manual assumes that you are using IBM Informix, Version 11.50.

You must install additional software to use the IBM Informix implementation of SNMP. For specific requirements, see Chapter 2, “IBM Informix implementation of SNMP,” on page 2-1.

The **onsnmp** utility cannot be run on HDR secondary servers, remote standalone (RS) secondary servers, or shared disk (SD) secondary servers.

Assumptions about your locale

IBM Informix products can support many languages, cultures, and code sets. All culture-specific information is brought together in a single environment, Global Language Support (GLS) locale.

This manual assumes that you use the U.S. 8859-1 English locale as the default locale. The default is **en_us.8859-1** (ISO 8859-1) on UNIX platforms or **en_us.CP1252** (Microsoft **1252**) for Windows environments. This locale supports U.S. English format conventions for dates, times, and currency, and also supports the ISO 8859-1 or Microsoft **1252** code set, which includes the ASCII code set plus many 8-bit characters such as é, è, and ñ.

If you plan to use nondefault characters in your data or your SQL identifiers, or if you want to conform to the nondefault collation rules of character data, you need to specify the appropriate nondefault locale.

For instructions on how to specify a nondefault locale, additional syntax, and other considerations related to GLS locales, see the *IBM Informix GLS User's Guide*.

Important: SNMPv1 and SNMPv2 do not recognize non-English code sets. For more information, see “GLS and SNMP” on page 2-14.

Demonstration databases

The DB-Access utility, which is provided with your Informix database server products, includes one or more of the following demonstration databases:

- The **stores_demo** database illustrates a relational schema with information about a fictitious wholesale sporting-goods distributor. Many examples in IBM Informix manuals are based on the **stores_demo** database.

- The **superstores_demo** database illustrates an object-relational schema. The **superstores_demo** database includes examples of extended data types, type and table inheritance, and user-defined routines.

For information about how to create and populate the demonstration databases, see the *IBM Informix DB–Access User’s Guide*. For descriptions of the databases and their contents, see the *IBM Informix Guide to SQL: Reference*.

The scripts that you use to install the demonstration databases reside in the **\$INFORMIXDIR/bin** directory on UNIX platforms and in the **%INFORMIXDIR%\bin** directory in Windows environments.

Example Code Conventions

Examples of SQL code occur throughout this publication. Except as noted, the code is not specific to any single IBM Informix application development tool.

If only SQL statements are listed in the example, they are not delimited by semicolons. For instance, you might see the code in the following example:

```
CONNECT TO stores_demo
...

DELETE FROM customer
    WHERE customer_num = 121
...

COMMIT WORK
DISCONNECT CURRENT
```

To use this SQL code for a specific product, you must apply the syntax rules for that product. For example, if you are using an SQL API, you must use EXEC SQL at the start of each statement and a semicolon (or other appropriate delimiter) at the end of the statement. If you are using DB–Access, you must delimit multiple statements with semicolons.

Tip: Ellipsis points in a code example indicate that more code would be added in a full application, but it is not necessary to show it to describe the concept being discussed.

For detailed directions on using SQL statements for a particular application development tool or SQL API, see the documentation for your product.

Additional Documentation

Documentation about this release of IBM Informix products is available in various formats.

All of the product documentation (including release notes, machine notes, and documentation notes) is available from the information center on the Web at <http://publib.boulder.ibm.com/infocenter/idshelp/v115/index.jsp>. Alternatively, you can access or install the product documentation from the Quick Start CD that is shipped with the product.

Compliance with Industry Standards

IBM Informix products are compliant with various standards.

IBM Informix SQL-based products are fully compliant with SQL-92 Entry Level (published as ANSI X3.135-1992), which is identical to ISO 9075:1992. In addition, many features of IBM Informix database servers comply with the SQL-92 Intermediate and Full Level and X/Open SQL Common Applications Environment (CAE) standards.

The IBM Informix Geodetic DataBlade Module supports a subset of the data types from the Spatial Data Transfer Standard (SDTS)—Federal Information Processing Standard 173, as referenced by the document Content Standard for Geospatial Metadata, Federal Geographic Data Committee, June 8, 1994 (FGDC Metadata Standard).

IBM Informix Dynamic Server (IDS) Enterprise Edition, Version 11.50 is certified under the Common Criteria. For more information, see *Common Criteria Certification: Requirements for IBM Informix Dynamic Server*, which is available at <http://www.ibm.com/e-business/linkweb/publications/servlet/pbi.wss?CTY=US&FNC=SRX&PBL=SC23-7690-00>.

Syntax Diagrams

Syntax diagrams use special components to describe the syntax for statements and commands.

Table 2. Syntax Diagram Components
















Component represented in PDF	Component represented in HTML	Meaning
	>>-----	Statement begins.
	----->	Statement continues on next line.
	>-----	Statement continues from previous line.
	-----><	Statement ends.
	-----SELECT-----	Required item.
	--+-----+-- '-----LOCAL-----'	Optional item.
	---+-----+--- +--DISTINCT---+ '---UNIQUE-----'	Required item with choice. One and only one item must be present.
	---+-----+--- +--FOR UPDATE---+ '--FOR READ ONLY--'	Optional items with choice are shown below the main line, one of which you might specify.
	.---NEXT-----. ---+-----+--- +---PRIOR---+ '---PREVIOUS-----'	The values below the main line are optional, one of which you might specify. If you do not specify an item, the value above the line will be used as the default.

Table 2. Syntax Diagram Components (continued)

Component represented in PDF	Component represented in HTML	Meaning
		Optional items. Several items are allowed; a comma must precede each repetition.
		Reference to a syntax segment.
<p>Table Reference</p> 	<p>Table Reference</p> 	Syntax segment.

How to Read a Command-Line Syntax Diagram


Command-line syntax diagrams use similar elements to those of other syntax diagrams.

Some of the elements are listed in the table in Syntax Diagrams.

Creating a No-Conversion Job








Notes:

1 See page Z-1

This diagram has a segment named “Setting the Run Mode,” which according to the diagram footnote is on page Z-1. If this was an actual cross-reference, you would find this segment in on the first page of Appendix Z. Instead, this segment is shown in the following segment diagram. Notice that the diagram uses segment start and end components.

Setting the Run Mode:



To see how to construct a command correctly, start at the top left of the main diagram. Follow the diagram to the right, including the elements that you want. The elements in this diagram are case sensitive because they illustrate utility syntax. Other types of syntax, such as SQL, are not case sensitive.

The Creating a No-Conversion Job diagram illustrates the following steps:

1. Type **onpladm create job** and then the name of the job.
2. Optionally, type **-p** and then the name of the project.
3. Type the following required elements:
 - **-n**
 - **-d** and the name of the device
 - **-D** and the name of the database
 - **-t** and the name of the table
4. Optionally, you can choose one or more of the following elements and repeat them an arbitrary number of times:
 - **-S** and the server name
 - **-T** and the target server name
 - The run mode. To set the run mode, follow the Setting the Run Mode segment diagram to type **-f**, optionally type **d**, **p**, or **a**, and then optionally type **l** or **u**.
5. Follow the diagram to the terminator.

Keywords and Punctuation

Keywords are words reserved for statements and all commands except system-level commands.

When a keyword appears in a syntax diagram, it is shown in uppercase letters. When you use a keyword in a command, you can write it in uppercase or lowercase letters, but you must spell the keyword exactly as it appears in the syntax diagram.

You must also use any punctuation in your statements and commands exactly as shown in the syntax diagrams.

Identifiers and Names

Variables serve as placeholders for identifiers and names in the syntax diagrams and examples.

You can replace a variable with an arbitrary name, identifier, or literal, depending on the context. Variables are also used to represent complex syntax elements that are expanded in additional syntax diagrams. When a variable appears in a syntax diagram, an example, or text, it is shown in *lowercase italic*.

The following syntax diagram uses variables to illustrate the general form of a simple SELECT statement.

►—SELECT—*column_name*—FROM—*table_name*—►

When you write a SELECT statement of this form, you replace the variables *column_name* and *table_name* with the name of a specific column and table.

How to Provide Documentation Feedback

You are encouraged to send your comments about IBM Informix user documentation.

Use one of the following methods:

- Send e-mail to docinf@us.ibm.com.
- Go to the information center at <http://publib.boulder.ibm.com/infocenter/idshep/v115/index.jsp> and open the topic that you want to comment on. Click the feedback link at the bottom of the page, fill out the form, and submit your feedback.
- Add comments to topics directly in the Informix information center and read comments that were added by other users. Share information about the product documentation, participate in discussions with other users, rate topics, and more! Find out more at <http://publib.boulder.ibm.com/infocenter/idshep/v115/topic/com.ibm.start.doc/contributing.htm>.

Feedback from all methods is monitored by those who maintain the user documentation. The feedback methods are reserved for reporting errors and omissions in our documentation. For immediate help with a technical problem, contact IBM Technical Support. For instructions, see the IBM Informix Technical Support website at <http://www.ibm.com/planetwide/>.

We appreciate your suggestions.

Chapter 1. SNMP concepts

What the SNMP is	1-1
Purpose of the SNMP.	1-1
SNMP architecture.	1-1
SNMP network managers	1-2
Master agents	1-4
Subagents.	1-4
Managed components.	1-4
Event notification	1-4
Data requests	1-5
Traps	1-5
MIBs	1-5
MIB table naming conventions.	1-5
The MIB hierarchy.	1-5

What the SNMP is

The Simple Network Management Protocol (SNMP) is a published, open standard for network management. SNMP lets hardware and software components on networks provide information to network administrators. This chapter provides a brief introduction to SNMP.

Purpose of the SNMP

Although the original purpose of the SNMP was to let network administrators remotely manage an Internet system, the design of SNMP lets network administrators manage applications as well as systems. SNMP provides the following capabilities:

- Hides the underlying system network
- Lets you manage and monitor all network components from one console

SNMP architecture

As Figure 1-1 illustrates, the SNMP architecture includes the following layers:

- SNMP Network Managers
- Master agents
- Subagents
- Managed components




Figure 1-1. SNMP architecture

A network can have multiple SNMP Network Managers. Each workstation can have one master agent. The SNMP Network Managers and master agents use SNMP protocols to communicate with each other. Each managed component has a corresponding subagent and MIBs. SNMP does not specify the protocol for communications between master agents and subagents.

SNMP network managers

An SNMP Network Manager is a program that asks for information from master agents and displays that information. Most SNMP Network Managers let you select the items to monitor and the form in which to display the information. An SNMP Network Manager typically provides the following features:

- Remote monitoring of managed components
- Low-impact sampling of the performance of a managed component
- Correlation of managed component metrics with related system and network metrics
- Graphical presentation of information

Many hardware and network services have created SNMP Network Managers. For example:

- CA-Unicenter
- Hewlett-Packard Open View
- IBM Netview/6000
- Novell Network Management System
- Sun Solstice
- Tivoli® TME 10 NetView®

SNMP Network Managers use a connectionless protocol, which means that each exchange between an SNMP Network Manager and a master agent is a separate transaction. A connectionless protocol allows the SNMP Network Manager to perform the following actions:

- Gather information without putting an excessive load on the network
- Function in an environment where heavy traffic can cause network problems

Most SNMP Network Managers provide a graphical user interface (GUI) such as the one that Figure 1-2 illustrates. With this SNMP Network Manager, you select a node to monitor and then choose specific information from a menu.




Figure 1-2. SNMP Network Manager example

Figure 1-3 shows how an SNMP Network Manager might display information about the databases on a network. In this example, the network has only one database.

```
Feb 17 1999 [ smoke ] : RDBMS-MIB.rdbmsDbTable
KEY = 72000003
rdbmsDbName = CustomerData
rdbmsDbName.72000003 = AnotherData
rdbmsDbPrivateMibOID = 1.3.6.1.4.1.893
rdbmsDbVendorName = IBM Corporation
rdbmsDbName = CustomerData
rdbmsDbContact = John Doe
```

Figure 1-3. Example of Monitoring Information

Figure 1-4 shows how a different SNMP Network Manager could display the same information.

```
rdbmsDbPrivateMibOID.72000003 = 1.3.6.1.4.1.893
rdbmsDbVendorName.72000003 = IBM Corporation
rdbmsDbName.72000003 = CustomerData
rdbmsDbContact.72000003 = John Doe
```

Figure 1-4. Example of monitoring information

In addition to text, an SNMP Network Manager might also display graphs or charts, as Figure 1-5 illustrates.




Figure 1-5. Example of monitoring information

Master agents

A master agent is a software program that provides the interface between an SNMP Network Manager and a subagent. Each workstation that includes a managed component needs to have a master agent. Each managed workstation can have a different master agent. A master agent performs the following tasks:

1. Parses requests from the SNMP Network Manager
2. Routes requests from the SNMP Network Manager to the subagents
3. Collects and formats responses from the subagents
4. Returns the responses to the SNMP Network Manager
5. Notifies the SNMP Network Manager when a request is invalid or information is unavailable

Subagents

A subagent is a software program that provides information to a master agent. Each managed component has a corresponding subagent. A subagent performs the following tasks:

1. Receives requests from the master agent
2. Collects the requested information
3. Returns the information to the master agent
4. Notifies the master agent when a request is invalid or information is unavailable

Managed components

A managed component is hardware or software that provides a subagent. For example, database servers, operating systems, routers, and printers can be managed components if they provide subagents.

Event notification

When an event occurs that affects the performance or availability of a managed component, the SNMP Network Manager can alert you to that condition. The following list describes some of the decisions that you can make about event notification:

- Define the conditions that should be monitored.

- Specify how frequently to poll for each condition.
When you determine the polling frequency, you must balance the need for prompt notification of an undesirable condition and the burden that polling puts on the network.
- Specify how the SNMP Network Manager notifies you of an event.
You might choose to have an icon blink or change colors when an event occurs.

Data requests

A data request can be a one-time request or a periodic request. A one-time request is useful for comparing the data for two managed components. Periodic requests are useful for accumulating statistical information about a managed component.

Traps

You can configure the SNMP Network Manager to detect extraordinary events and notify you when they occur. The following list describes some of the decisions that you can make about traps:

- Define the conditions that should generate a trap.
- Specify how the SNMP Network Manager notifies you of a trap.
You might choose to have an icon blink or change colors when a trap occurs.

- Specify how the SNMP Network Manager responds to a trap.

The SNMP Network Manager can query the managed component to determine the cause and extent of the problem.

MIBs

A Management Information Base (MIB) is a group of tables that specify the information that a subagent provides to a master agent. MIBs follow SNMP protocols.

MIBs use a common interface definition language. The Structure of Management Information (SMI) defines this language and dictates how to use Abstract Syntax Notation One (ASN.1) to describe each table in the MIBs.

MIB table naming conventions

The name of each MIB table starts with the name of the MIB. Thus each table in the RDBMS MIB starts with **rdbms**. For example, the RDBMS MIB includes tables that are named **rdbmsSrvTable** and **rdbmsDbInfoTable**.

The name of each column in an MIB table starts with the name of the table, excluding **Table**. Thus, each column in **rdbmsSrvTable** starts with **rdbmsSrv**. For example, **rdbmsSrvVendorName** and **rdbmsSrvProductName** are columns in **rdbmsSrvTable**.

The MIB hierarchy

All MIBs are part of an information hierarchy that the Internet Assigned Numbers Authority (IANA) defines. The hierarchy defines how to name tables and columns and how to derive the numerical object identifiers (OIDs). Figure 1-6 shows the MIB hierarchy.




Figure 1-6. MIB hierarchy

Even though you rarely see the full path to a table, column, or value, the path is important because the SNMP components use the numerical equivalent of the path to locate data. For example, the following value is the path to the Application MIB:
 iso.org.dod.internet.mgmt.mib-2.application

An OID is the numerical equivalent of a path. It uniquely describes each piece of data that an SNMP Network Manager can obtain and is written as a string of numbers separated by periods (.). For example, the following value is the OID for the Application MIB:
 1.3.6.1.2.1.27

The following value is the OID for a value in the Application MIB:
 1.3.6.1.2.1.27.1.1.8.2

The first part of this OID is the OID for the Application MIB. The final part of the OID assigns values sequentially to each table in the MIB, each column in the table, and each value in a column.

Chapter 2. IBM Informix implementation of SNMP

Components of the Informix implementation	2-1
Purpose of IBM Informix SNMP	2-2
Event notification	2-2
Data requests	2-2
Traps	2-3
Information that OnSNMP provides	2-3
SNMP standard.	2-3
SNMP architecture.	2-4
IBM Informix SNMP architecture on UNIX	2-4
IBM Informix SNMP architecture on Windows	2-4
Using SNMP on UNIX or Linux	2-5
The runsnmp.ksh script	2-6
UNIX master agents	2-6
Assuring compatibility	2-7
Installing and configuring a master agent manually.	2-7
Starting and stopping a master agent	2-8
UNIX subagent	2-9
UNIX server discovery process	2-9
Preparing onsrvpd manually	2-9
Issuing the onsrvpd command	2-10
Choosing an installation directory	2-11
Using SNMP on Windows	2-11
Windows Master Agent.	2-11
Windows subagent	2-11
Starting and stopping OnSNMP	2-12
Configuring OnSNMP	2-12
Windows registry key for the OnSNMP logging level.	2-13
Windows server discovery process	2-13
Starting and stopping onsrvpd	2-13
Installing the IBM Informix SNMP agent	2-14
GLS and SNMP	2-14
MIBs	2-14
Application MIB	2-14
RDBMS MIB	2-15
Informix private MIB	2-15
Online MIB.	2-16
MIB objects.	2-16
Table indexing.	2-17
Numeric index values	2-17
Alphabetical index values	2-17
Refresh control value	2-18
Files installed for SNMP	2-18
Files installed on UNIX or Linux	2-18
Files installed on Windows	2-19

Components of the Informix implementation

The IBM Informix implementation consists of the following components:

- Master agent

UNIX Only

- On UNIX, a master agent is provided through licensing agreements with vendors. See “UNIX master agents” on page 2-6.

Windows 2000 Only

- On Windows, install the Microsoft SNMP Extendible master agent.

End of Windows 2000 Only

- Subagent
The subagent for Informix database servers is OnSNMP.
- Managed components
In the IBM Informix implementation of SNMP, each database server is a managed component.
- MIBs
OnSNMP uses several MIBs.

Purpose of IBM Informix SNMP

The IBM Informix implementation of SNMP lets database administrators monitor Informix database servers and databases.

Event notification

You can configure an SNMP Network Manager to notify you when a specific event occurs. An event usually has a corresponding object in an MIB table. The following table describes four possible events and the MIB objects that correspond to them.

Event	MIB object
A database server is not available.	onServerMode
Database availability changed.	rdbmsRelState
A chunk failed.	onChunkStatus
A table is running out of space.	onTablePagesAllocated onTablePagesUsed

For example, you might discover that an application that uses an Informix database server stopped responding. You can send email to the help desk to report this problem. The help desk can tell you about the problem, and you can look at **onSessionTable** to determine the cause of the problem.

Data requests

You can issue a one-time data request to compare the configuration parameters of two database servers. You can issue periodic data requests to provide statistical information for assessing database performance or resource allocation.

For example, even if you use a database that is on a local host, you can call a remote technical support representative to report a problem. The problem might be that the data for the transactions running in a particular situation is less than expected. From the remote location, the technical support representative can query an SNMP Network Manager to determine the database server configuration, monitor the database server performance, and identify the bottleneck. OnSNMP provides this information to SNMP Network Managers through the master agent.

Traps

When the status of the database server changes from its current status to any status that is less available, OnSNMP sends a message to the SNMP Network Managers. For example, if a dbspace goes down, the database server status changes from full to limited availability. The message that OnSNMP sends is **rdbmsStateChange**, which is an unsolicited trap. When an SNMP Network Manager notifies you that it received an **rdbmsStateChange** trap, you can query the database server that generated the trap to determine the cause and extent of the problem.

For example, the logical logs for a database server might become full and cause the database server to become unavailable. OnSNMP can notice that the database server is unavailable and send an **rdbmsStateChange** trap to an SNMP Network Manager. The SNMP Network Manager can make an icon blink to notify you of the problem. You can then send data requests to determine the cause of the failure.

For information about traps and the EMANATE master agent, see “Installing and configuring a master agent manually” on page 2-7.

Information that OnSNMP provides

All the information that OnSNMP provides is available from other sources, such as the system catalog tables, the **sysmaster** and **sysutils** databases, dbaccess calls, and the **onstat** utility. However, the system catalog tables and the **onstat** utility refer only to a single database, and the **sysmaster** and **sysutils** databases refer only to a single database server. OnSNMP provides information that lets an SNMP Network Manager monitor all the Informix databases that are on a network. Figure 2-1 illustrates this concept.




Figure 2-1. Monitoring Informix databases

SNMP standard

The SNMP standard has two versions: SNMPv1 and SNMPv2. The following table lists the versions of the SNMP standard with which OnSNMP complies.

Operating System	Version of the SNMP Standard
UNIX	SNMPv1 and SNMPv2

SNMP architecture

The architecture for the IBM Informix implementation of SNMP depends on your operating system.

SNMP is incompatible on High-Availability Data Replication (HDR) secondary servers, remote standalone (RS) secondary servers, or shared disk (SD) secondary servers.

IBM Informix SNMP architecture on UNIX

Figure 2-2 shows the SNMP architecture for Informix database servers on UNIX. Each managed workstation runs one master agent and one server discovery process. Each database server has one OnSNMP process.




Figure 2-2. IBM Informix SNMP architecture on UNIX

IBM Informix SNMP architecture on Windows

Figure 2-3 on page 2-5 shows the SNMP architecture for Informix database servers on Windows. Each managed workstation runs one master agent. The master agent and the SNMP Network Manager use SNMP to communicate with each other. Each managed workstation runs one server discovery process and one **infxsnmp.dll**. One instance of the **onsnmp** subagent is started for each instance of Informix that runs on the managed workstation. OnSNMP and the master agent do not need to use SNMP to communicate with each other.




Figure 2-3. IBM Informix SNMP Architecture on Windows

Using SNMP on UNIX or Linux

To use the IBM Informix implementation of SNMP on UNIX or Linux, you must install and start the following software:

- **runsnmp.ksh**
- An SNMP Network Manager on a network management workstation
- A master agent on each workstation that includes an Informix database server
- An Informix database server


When you install an Informix database server, the installation procedure installs the OnSNMP subagent and the server discovery process as well as the files needed for SNMP support.

The discovery process discovers multiple server instances running on the host. These instances might belong to different versions that are installed on different directories. Whenever a server instance is brought online, the discovery process detects it and spawns an instance of OnSNMP to monitor the database server.

For information on how **runsnmp.ksh** automatically sets up and starts SNMP on UNIX, see “The runsnmp.ksh script” on page 2-6. The rest of this section describes how to do a manual setup and provides background information that you can use to diagnose setup problems.

The runsnmp.ksh script

The **runsnmp.ksh** script on UNIX ensures that both the SNMP master agent and the **onsrvapd** server-discovery daemon are running on a host. The **runsnmp.ksh** file is in the **\$INFORMIXDIR/snmp** directory. You must correctly set the **INFORMIXDIR** environment variable to the latest installed version of the product and run the script as **root**.



Issue the **runsnmp.ksh** commands that the following diagram shows.

Option	Description
-m <i>master_agent_args</i>	The master-agent arguments can be either stop or valid master-agent arguments.
-s <i>server_disc_args</i>	The server-discovery arguments can be either stop or valid onsrvapd arguments.
start	Starts snmpdm and onsrvapd if they are not running. This option is the default.
stop	Stops snmpdm and onsrvapd if they are already running and exits.

The *master_agent_args* and the *server_disc_args* are not checked for correctness.

The following examples illustrate how to use **runsnmp.ksh**:

- Start **snmpdm** and **onsrvapd** if they are not running.
runsnmp.ksh
- Stop **onsrvapd** and **subagents** and then exit.
runsnmp.ksh -s stop
- Stop **onsrvapd** and any **subagents** and then restart **onsrvapd**.
runsnmp.ksh -s stop start
- Stop **snmpdm**, **onsrvapd**, and any **subagents** and then exit.
runsnmp.ksh stop
- Stop **snmpdm** or **snmpdp**, **onsrvapd**, and any **subagents** and then restart **snmpdm** or **snmpdp** and **onsrvapd**.
runsnmp.ksh stop start
- Start **snmpdm** if it is not running, and then start **onsrvapd** with the none option, if it is not running.
runsnmp.ksh -s "-none"

UNIX master agents

On UNIX, master agents are provided through licensing agreements. The following table lists these master agents.

Master Agent	Company	Web Site Home Page
EMANATE, Version 14.2	SNMP Research	www.snmp.com

For some UNIX platforms, you might be able to use a master agent other than the one provided with the database server. To see whether this applies to your platform, see your release notes.

Assuring compatibility

The following guidelines assure master agent compatibility:

- Only one master agent is provided, usually EMANATE, for each UNIX platform type.
- The subagent that works with the master agent is also provided with the database server.
- In some cases, the platform vendor also supplies a master agent that works with the subagent provided with the database server. This is generally true only if the platform vendor supplies the same type of master agent as that provided with the database server and if the version number of the vendor-supplied master agent is greater than or equal to that of the version provided with the database server.
- You should run only one instance of a master agent on a platform. You can run multiple instances of subagents, including multiple instances of **onsnmp**, if multiple database server instances exist.
- Informix subagents can coexist with subagents that platform or third-party vendors supply if all the subagents share a common, compatible master agent.

Installing and configuring a master agent manually

The **runsnmp.ksh** script automatically performs the steps in this section for the master agents provided with the database server. If you bought a master agent from another vendor, follow the installation instructions that the vendor provides.

To configure the EMANATE master agent:

1. Set the following environment variables:
 - Make sure that the **PATH** environment variable includes **\$INFORMIXDIR/bin**.
 - Set **SR_AGT_CONF_DIR** to the directory for the EMANATE configuration file.
 - Set **SR_LOG_DIR** to the directory for the EMANATE log file.

The EMANATE configuration files are located in the **\$INFORMIXDIR/snmp/snmpr** directory. The log files are located in the **/tmp** directory. The **/tmp** directory is the default location if the variable is not set.
2. Make sure that either the Network Information Services or the **/etc/services** file configures UDP ports 161 and 162 as the SNMP ports.
 - a. Use the **grep** command to search **/etc/services** for **snmp**. The output from **grep** should be similar to the following lines:


```
snmp          161/udp
snmp-trap     162/udp
```
 - b. Make sure that UDP port 161 is available so that the master agent can be the owner of the port.
3. Add the following line to the **snmp** configuration file for the **snmpd** daemon to accept messages from **onsnmp**:


```
smuxpeer 0.0
```

If this line does not exist, and the snmpd daemon is log enabled, the following message is reported:

```
snmpd log:
refused smux peer: oid SNMPv2-SMI::zeroDotZero, password , descr rdbms subagent
onsrvapd log:
INFO : onsrvapd pid 9045, poll 5 secs, linger 5 mts, logfile
/tmp/onsrvapd.42f0d7392355.log.
MAJOR: signalCatcher - Caught SIGCHLD.
MAJOR: childKilled - Subagent pid 9046 Status 65280.
onsnmp log:
MAJOR: SMUX subagent failed to instantiate managed row
```

Starting and stopping a master agent

Start the master agent before you start an Informix database server, and stop all Informix database servers on a workstation before you stop the master agent.

The best way to start a master agent is to run the **runsnmp.ksh** script as part of the startup procedure for the system. Similarly, the best way to stop a master agent is to run the **runsnmp.ksh** script as part of the shutdown procedure. However, you can start or stop a master agent manually if you prefer. Additionally, while a master agent is running, you can make sure that it is running correctly.

If you bought a master agent from another vendor, follow the instructions that the vendor provides.

Starting and stopping a master agent automatically: The **runsnmp.ksh** script automatically starts the EMANATE master agent at startup and stops it at shutdown.

Starting and stopping a master agent manually: This section describes how to start or stop a master agent if you do not use the **runsnmp.ksh** script.

To start a master agent manually:

1. Log in as **root**.
If you do not have **root** user privileges, ask your system administrator to start the master agent.
2. Stop or kill any master agents and daemons that are running on the workstation.
3. Enter the following command:
For EMANATE:
`snmpdm &`

To stop a master agent manually:

1. Log in as **root**.
If you do not have **root** user privileges, ask your system administrator to stop the master agent.
2. Kill the following process:
For EMANATE, **snmpdm**

The following table describes the command-line options that you can include in the `snmpdm` command for the EMANATE master agent.

Option	Description
-apall	Turn on all messages.

-aperror	Turn on error messages. Error messages are already turned on by default.
-aptrace	Turn on trace messages.
-apwarn	Turn on warning messages. Warning messages are already turned on by default.
-d	Run the master agent in the foreground.

To make sure that a master agent is running correctly:

1. Check the master agent log file to verify that the master agent has not generated any errors. The log file is located in the **/tmp** directory unless the environment variable mentioned in on page 2-7 is set to a different directory.
2. Verify that the process is running:
For EMANATE, **snmpdm**

UNIX subagent

When you install an Informix database server on UNIX, the installation procedure installs OnSNMP. OnSNMP consists of the **onsnmp** program.

Under normal circumstances, you do not need to start or stop OnSNMP explicitly. If you experience abnormal circumstances and need to start or stop OnSNMP explicitly, contact Technical Support. For contact information, refer to your *IBM Informix Installation Guide*.

The following additional files are provided with the database server for SNMP support.

Program	Description
onsrvapd daemon	When you start an Informix database server that is on this workstation, onsrvapd detects this event and starts OnSNMP for the database server. When the database server halts, onsrvapd stops OnSNMP for that database server. See “UNIX server discovery process” on page 2-9.
runsnmp.ksh script	This script starts onsrvapd . It also starts the master agent that is appropriate for the platform. If you want to run OnSNMP, you need to run runsnmp.ksh each time that you reboot. See “The runsnmp.ksh script” on page 2-6.

UNIX server discovery process

The **runsnmp.ksh** script automatically starts the UNIX server discovery process, as “The runsnmp.ksh script” on page 2-6 describes. This section provides procedures for working manually with **onsrvapd**. Some of these procedures include instructions on how to configure OnSNMP.

The principles for starting and stopping **onsrvapd** manually are the same as those for a master agent: start **onsrvapd** before you start an Informix database server, and stop all Informix database servers on a workstation before you stop **onsrvapd**.

Preparing onsrvapd manually

If you do not use **runsnmp.ksh** to automatically prepare and start **onsrvapd**, perform the steps in this section.

To prepare onsrvapd:

1. Make sure that the owner of **onsrvapd** is **root** and that the group is **informix**.
2. Make sure that the setuid (sticky) bit is set for the **onsrvapd** file.

Issuing the onsrvapd command

You can specify the **onsrvapd** command-line options that Figure 2-4 shows. Some of these options affect OnSNMP.




Figure 2-4. onsrvapd Command

Option	Description
-d	Flag that tells UNIX to run onsrvapd once and terminate it instead of starting it as a daemon.
-g logginglevel	Logging level to which OnSNMP logs debug information. Valid values are 2, 4, 8, 16, 32, and 64. The default value is 32. The lower the value, the higher the amount of logging. The onsrvapd daemon passes this value to OnSNMP.
-k lingersmmts	Number of minutes that onsrvapd waits after a database server goes down before onsrvapd kills the corresponding OnSNMP. If <i>lingersmmts</i> is 0, onsrvapd waits indefinitely.
-l pathname	Directory for the error log files. The filename of the OnSNMP error log is onsnmp.servername.log . For example, if your server name is MyServer, the filename of the OnSNMP error log is onsnmp.MyServer.log . The filename of the onsrvapd error log is onsrvapd.log .
-p pollsecs	Frequency, in seconds, with which OnSNMP polls the database server. The default value is 5 seconds. The onsrvapd daemon passes this value to OnSNMP.
-r level	Refresh control value. For a description, see "Refresh control value" on page 2-18.
-V	Prints the OnSNMP version number.

To start onsrvapd manually:

1. Stop or kill any daemons that are running on the workstation.
2. Enter the following command:
`onsrvapd`

To stop **onsrvapd** manually, kill the **onsrvapd** process.

To make sure that onsrvapd is running correctly:

1. Check the log file to verify that **onsrvapd** has not generated any errors. The log file is located in the **/tmp** directory.
2. Verify that **onsrvapd** is running.

Choosing an installation directory

When you have multiple Informix installation directories on a host computer, you must set the latest installation directory as **INFORMIXDIR** before you run the **runsnmp.ksh** script to start OnSNMP. If all the directories are for the same type of database server, use the installation directory that has the latest database server version number.

One way to determine the latest directory to use with different types of database server lines is to find the latest version of the SNMP master agent. The EMANATE master agent displays the version when you run it.

Using SNMP on Windows

To use the IBM Informix implementation of SNMP on Windows, you must install and start the following software:

- Microsoft's SNMP service on each workstation that includes an Informix database server
- An Informix database server

When you install an Informix database server, the installation procedure installs the OnSNMP subagent and the server discovery process as well as the files needed for SNMP support.

Windows Master Agent

The Microsoft TCP/IP custom installation procedure installs the Microsoft SNMP Extendible master agent. For information about this master agent, see the Microsoft TCP/IP Help.

To start the Microsoft TCP/IP Help:

1. Choose **Start > Help**.
2. Choose the **Index** tab.
3. Enter the following phrase in the text box:

SNMP

In response to this search request, the help system displays a **Topics Found** dialog box.

4. Choose **TCP/IP Procedures Help**.

Important: To start or stop the Microsoft SNMP Extendible master agent, you must be a member of the **Administrator Group** on the host workstation.

Windows subagent

On Windows, OnSNMP comprises the following files. The table also lists the directories in which the IBM Informix installation procedure installs each file.

File	Description	Directory
infxsnmp.dll	Library that provides the interface between onsnmp.exe and the master agent. The IBM Informix installation procedure installs one infxsnmp.dll on each workstation. The initialization process for the master agent loads infxsnmp.dll .	%Windows%\system32

File	Description	Directory
onsnmp.exe	Subagent program. The IBM Informix installation procedure installs an onsnmp.exe file for each database server.	%INFORMIXDIR%\bin
onsrvapd.exe	<p>Server discovery process, which starts onsnmp.exe for each database server that starts. The IBM Informix installation procedure performs the following tasks for onsrvapd.exe:</p> <ul style="list-style-type: none"> • Installs one onsrvapd.exe on each workstation • Creates the Informix Server Discovery Process for SNMP in the control panel and configures it to start automatically when the system reboots 	%Windows%\system32

When you install an Informix database server, the installation procedure automatically installs OnSNMP. When you start an Informix database server that is on a network that uses SNMP, **onsrvapd.exe** detects this event and starts OnSNMP for the database server. When the database server halts, **onsrvapd.exe** stops OnSNMP for that database server.

Starting and stopping OnSNMP

Under normal circumstances, you do not need to start or stop OnSNMP explicitly. If you are experiencing abnormal circumstances and need to start or stop OnSNMP explicitly, contact Technical Support. For contact information, refer to your *IBM Informix Installation Guide*.

Configuring OnSNMP

The Informix installation procedure creates a new registry key, **OnSnmSubagent**, under **HKEY_LOCAL_MACHINE\SOFTWARE\Informix**.

The following table describes the **OnSnmSubagent** arguments that you can change.

Argument	Value	Description
Environment\LINGER_TIME	<i>lingermts</i>	Number of minutes that the master agent waits after a database server goes down before the master agent kills the corresponding OnSNMP. If <i>lingermts</i> is 0, the master agent waits indefinitely.
Environment\LOGDIR	<i>pathname</i>	Complete path of the OnSNMP error-log file, including filename
Environment\REFRESH_TIME	<i>pollsecs</i>	Frequency, in seconds, with which OnSNMP polls the database server
Environment\LOGLEVEL	<i>loglevel</i>	Logging level to which OnSNMP logs debugging information. The default value is 3. The onsrvapd daemon passes this value to OnSNMP.

The following table describes the **OnSnmSubagent** arguments that you should not change.

Argument	Value	Description
Pathname	<i>pathname</i>	Complete path of infxsnmp.dll, including filename
MIBS\APPLMIB	<i>apploid</i>	OID for the Application MIB
MIBS\ONMIB	<i>onoid</i>	OID for the Online MIB
MIBS\RDBMSMIB	<i>rdbmsoid</i>	OID for the RDBMS MIB

The Informix installation procedure also creates a new argument, `INFXSNMP`, under `HKEY_LOCAL_MACHINE\SYSTEM\CurrentControlSet\Services\SNMP\Parameters\ExtensionAgents`. This new argument specifies the location of the `OnSnmpSubagent` registry key, including the name of the key.

To change the OnSNMP configuration, change the values for these arguments.

Windows registry key for the OnSNMP logging level

On Windows, there is a registry entry to specify the logging level to which OnSNMP logs debugging information.

The logging levels that you can specify are:

- 6 (fatal error conditions)
- 5 (major error conditions)
- 4 (warnings in the program)
- 3 (general information)
- 2 (debug information)
- 1 (dump all information)

Windows server discovery process

The Informix Server Discovery Process for SNMP is known as **onsrvapd**. It is installed as a Windows service that runs under the Informix user. The discovery process discovers multiple server instances running on the host. These instances might belong to different versions that are installed on different directories. Whenever a server instance is brought online, the discovery process detects it and spawns an instance of OnSNMP to monitor the database server.

Starting and stopping onsrvapd

You can start **onsrvapd** from the services folder in the control panel or from a command prompt. To start and stop **onsrvapd** from a command prompt, enter the following commands:

- To start **onsrvapd**, enter:
`net start onsrvapd`
- To stop **onsrvapd**, enter:
`net stop onsrvapd`

The OnSNMP Discovery Process (`onsrvapd.exe`) is installed as an Windows service and starts and stops automatically. You do not need to issue commands at the command line. In the event you want to issue commands from the command line, see the command-line syntax listed in “Issuing the `onsrvapd` command” on page 2-10.

To make sure that onsrvapd is running correctly:

1. Check the log file to verify that **onsrvapd** has not generated any errors. For location of the log files, see your release notes.
2. Verify that **onsrvapd** is running.

Installing the IBM Informix SNMP agent

If you install the Microsoft SNMP Extendible master agent after you install the IBM Informix database server, the Informix installation procedure cannot create INFxSNMP. To correct this problem, run a program called **inssnmp** to complete the OnSNMP installation.

To run inssnmp:

1. Start a Command Prompt session.
2. Go to %INFORMIXDIR%\bin.
3. Enter the following command:
`inssnmp`

Tip: If you install a Windows service pack on your computer before you install the Microsoft SNMP Extendible master agent, you might need to reinstall the service pack.

GLS and SNMP

IBM Informix products include a Global Language Support (GLS) feature, which lets you work with languages that use code sets other than the standard English code set. However, the SNMP protocols that OnSNMP supports (SNMPv1 and SNMPv2) do not recognize these different code sets.

OnSNMP uses the U.S. English locale when it sends information to the master agent. If OnSNMP cannot convert the code set of the database to the U.S. English locale, it fails and returns error -23101 with the following message:

Unable to load locale categories.

OnSNMP sends only 7-bit characters. If an eighth bit is present, OnSNMP truncates it. Thus, when an SNMP Network Manager requests character information, OnSNMP returns a value. However, the value might not reflect the name of the database or table.

OnSNMP sends numeric information correctly, regardless of the code set that the database uses.

MIBs

This section describes the types of MIBs and the types of MIB objects that the Informix database server uses. For a description of MIBs, see page 1-5.

OnSNMP uses the following MIBs:

- Application MIB
- Relational Database Management System (RDBMS) MIB
- Informix Private MIB
- Online MIB in the Informix Private MIB

Application MIB

The Application MIB is a public MIB, which means that the Internet Engineering Task Force (IETF) specifies the structure of the MIB and the MIB tables. A public MIB is the same for all managed components on an SNMP network, not just for IBM Informix products. OnSNMP uses only **applTable**, which is the portion of the

Application MIB that the RDBMS MIB requires. Figure 1-6 on page 1-6 shows the position of the Application MIB in the MIB hierarchy.

The following value is the path to the Application MIB:

`iso.org.dod.internet.mgmt.mib-2.application`

The following value is the OID for the Application MIB:

`1.3.6.1.2.1.27`

RDBMS MIB

The RDBMS MIB is a public MIB, which means that the IETF specifies the structure of the MIB and the MIB tables. A public MIB is the same for all managed database components. However, some of the definitions in the RDBMS MIB are purposely vague to let each vendor tailor the entries to a specific database server. For example, **rdbmsSrvLimitedResourceTable** contains information about the resources that a database server uses. Each database server vendor can decide which resources to include in this table. Figure 1-6 on page 1-6 shows the position of the RDBMS MIB in the MIB hierarchy.

The following value is the path to the RDBMS MIB:

`iso.org.dod.internet.mgmt.mib-2.rdbmsMIB`

The following value is the OID for the RDBMS MIB:

`1.3.6.1.2.1.39`

Informix private MIB

The Informix Private MIB is a private MIB, which means that a private enterprise defines and uses it. The Internet Assigned Numbers Authority (IANA) assigns a unique enterprise identifier to each company that uses the SNMP protocol. The Informix Private MIB describes information that is relevant to the specific architecture and features of Informix database servers and databases. Figure 2-5 shows the MIB hierarchy for the Informix Private MIB.




Figure 2-5. MIB Hierarchy for the Informix private MIB

The following value is the path to the Informix Private MIB:

iso.org.dod.internet.private.enterprises.informix

The following value is the OID for the Informix Private MIB:

1.3.6.1.4.1.893

Online MIB

The Online MIB is in the Informix Private MIB. The Online MIB contains information for all Informix database servers. In the Online MIB, all tables are below the following node:

servers.onlineMIB.onlineObjects

The OID for each table in the Online MIB starts with the following value:

1.3.6.1.4.1.893.1.1.1

MIB objects

An MIB object is similar to a column in a table. The IBM Informix implementation of SNMP recognizes the following types of MIB objects:

- Traps are defined as MIB objects, but they cannot be retrieved. Instead, when a certain condition is detected, OnSNMP issues an event that includes the object ID that the trap defines.
- Catalog-based MIB objects exist only if the refresh control value (described on page 2-18) is once or all.
- Enterprise Replication objects are tables that exist only if a database server is configured to participate in Enterprise Replication.

Table indexing

In the description of the MIBs in Chapter 3, the header for each table specifies how each row in the table is indexed. A table can have one or more indexes. For example, the header for **rdbmsSrvTable** is **rdbmsSrvTable[applIndex]**, which means that the table has one index called **applIndex**.

Each index value is concatenated to the column OID with periods between each value. If a MIB table has several indexes, the indexes are concatenated one after the other. Most SNMP Network Managers display only the final portion of the OID that relates to the table being displayed. Some SNMP Network Managers display the OID as part of the information about each individual item; other SNMP Network Managers display the OID as part of a header for a list of values.

Numeric index values

The following line is an example of indexed information:

```
rdbmsRelActiveTime.72000003.893072000 = 11/16/98 12:34:08
```

The following table describes how to interpret the example. For more information about these values, see “rdbmsRelTable” on page 3-5.

Index Subvalue	Description
rdbmsRelActiveTime	Name of the column
72000003	rdbmsDbIndex
893072000	applIndex

Alphabetical index values

When an index is an alphabetical string, such as the name of a configuration parameter, the OID for that index consists of the following elements, all separated by periods:

- Number of letters in the name
- ASCII value for each letter

The following line is an example of alphabetical indexed information:

```
rdbmsSrvParamCurrValue.893072000.4.76.82.85.83.1 = 8
```

The following table describes how to interpret this example. For more information about these values, see “rdbmsSrvParamTable” on page 3-7.

Index Subvalue	Description
rdbmsSrvParamCurrValue	Name of the column
893072000	applIndex
4.76.82.85.83	rdbmsSrvParamName:
	4 = Number of letters
	76 = L
	82 = R
	85 = U
	83 = S
1	rdbmsSrvParamSubIndex

Refresh control value

As a background task, OnSNMP periodically updates the contents of MIB tables that it derives from catalog information. The refresh control value determines the amount of time that OnSNMP spends refreshing these MIB tables versus the amount of time that it spends responding to queries from the master agent.

Specify the refresh control value with the **runsnmp.ksh -s -r** command-line option or the **onsrvapd -r** command-line option. The following table lists the MIB tables that this value affects. See also “Issuing the onsrvapd command” on page 2-10.

Database-Related MIB Tables	Table-Related MIB Tables
rdbmsDbInfoTable rdbmsDbTable rdbmsRelTable onBarTable onDatabaseTable	onActiveTableTable onFragmentTable onTableTable

The following table describes the possible values for the refresh control value.

Value	Description
a or all	Refresh the database-related and table-related tables periodically.
n or none	Do not fill or refresh any of the catalog-based tables. Instead, leave the catalog-based tables empty.
o or once	Fill the database-related and table-related tables once at startup.

The following table lists the default refresh control value for each operating system.

Operating System	Default Refresh Control Value
UNIX	once
Windows	all

The best value to use depends on the environment and how you use OnSNMP. If the list of tables and databases changes frequently, it is probably best to use a value of all to make sure that the MIB tables are accurate. If the environment includes many tables and databases, it is probably best to use a value of once to let OnSNMP respond to queries.

Files installed for SNMP

This section lists the files that are typically installed for the IBM Informix implementation of SNMP on UNIX and Windows.

Files installed on UNIX or Linux

The **runsnmp.ksh** file exists for all UNIX versions of SNMP support.

The following files are installed in **\$INFORMIXDIR/bin**.

Filename	Description
onsnmp	OnSNMP executable
onsrvapd	Server discovery process
snmpdm	EMANATE executable or a dummy file for UNIX platforms that EMANATE does not support

The following files are installed in **\$INFORMIXDIR/snmp**.

Filename	Description
Files for the MIBs:	
./snmpr/snmpd.cnf	EMANATE configuration file or a dummy file for UNIX platforms that EMANATE does not support
.runsnmp.ksh	Script that starts the master agent and onsrvapd

OnSNMP uses the following log files by default.

Filename	Description
snmp.log	Log file for EMANATE; not installed on UNIX platforms that EMANATE does not support
onsrvapd.log	Log file for onsrvapd.
onsnmp.*.log	Log file for onsnmp.

For Informix, the path is **onsnmp.servername.log**

Files installed on Windows

The following files are created in **%Windows%\system32**.

Filename	Description
infxsnmp.dll	DLL for OnSNMP
onsrvapd.exe	Server discovery process

The following file is created in **%INFORMIXDIR%\bin**.

Filename	Description
onsnmp.exe	OnSNMP executable

In addition, log files are created in the directories that are specified in the registry.

Chapter 3. MIB reference

MIBs that OnSNMP uses.	3-1
Application MIB	3-2
applTable	3-2
RDBMS MIB.	3-4
rdbmsDbInfoTable	3-4
rdbmsDbLimitedResourceTable	3-4
rdbmsDbParamTable	3-5
rdbmsDbTable	3-5
rdbmsRelTable	3-5
rdbmsSrvInfoTable.	3-6
rdbmsSrvLimitedResourceTable	3-6
rdbmsSrvParamTable	3-7
rdbmsSrvTable	3-8
rdbmsTraps	3-8
frdbmsStateChange trap	3-8
Online MIB in the Informix private MIB	3-9
onActiveBarTable	3-9
onActiveTableTable	3-9
onBarTable	3-10
onChunkTable	3-11
onDatabaseTable	3-12
onDbospaceTable	3-13
onErQueueTable	3-14
onErSiteTable	3-14
onFragmentTable	3-16
onLockTable	3-17
onLogicalLogTable	3-18
onPhysicalLogTable	3-18
onServerTable	3-19
onSessionTable.	3-20
onSqlHostTable	3-22
onTableTable	3-23

MIBs that OnSNMP uses

An SNMP Network Manager hides most of the structure of the MIBs. However, an understanding of this structure can help you comprehend the information that an SNMP Network Manager displays.

The descriptions in this chapter are brief. For detailed descriptions, see the online MIB files. The following table lists the directories for the MIB files.

Operating System	MIB Directory
UNIX	<code>\$INFORMIXDIR/snmp</code>
Windows	<code>%INFORMIXDIR%\etc</code>

Many MIB values are for database servers, depending on the types of database servers that you are using.

This chapter presents the MIB tables in alphabetical order. For the logical order, see the MIB files. The following table summarizes the MIB tables that OnSNMP uses and indicates the page that contains more information.

MIB	Table	Description
Application (See page 3-2)	applTable	Attributes for each database server
RDBMS (See page 3-4)	rdbmsDbInfoTable	Information about databases
	rdbmsDbTable	Information about databases
	rdbmsRelTable	Information about the relationship between a database and the database server with which it is associated
	rdbmsSrvInfoTable	Information about the database server since it was started
	rdbmsSrvLimited-ResourceTable	Information about the limited resources for each database server
	rdbmsSrvParamTable	Information about the configuration parameters for each database server
	rdbmsSrvTable	Information about a database server
	rdbmsTraps	Information about the traps that OnSNMP can send to the SNMP Network Manager
Online (See page 3-9)	onActiveBarTable	Information about the current ON-Bar activity
	onActiveTableTable	Information about the open and active database tables
	onBarTable	Information about the backup and restore history
	onChunkTable	Information about the chunks that the database servers use
	onDatabaseTable	Information about active databases
	onDbospaceTable	Information about dbspaces
	onErQueueTable	Information about the Enterprise Replication queue
	onErSiteTable	Information about the Enterprise Replication site
	onFragmentTable	Information about the fragments that are in fragmented database tables
	onLockTable	Information about the active locks that database servers are using
	onLogicalLogTable	Information about logical logs
	onPhysicalLogTable	Information about physical logs
	onServerTable	Status and profile information about each active database server
	onSessionTable	Information about each session
	onSqlHostTable	Copy of the connection information
	onTableTable	Information about a database table

Application MIB

Informix uses one table from the application MIB. This table provides general-purpose attributes for each database server.

applTable

The following list summarizes this table:

Contents: Attributes for each database server

Index: applIndex

Scope of a row: One database server

The table has the following MIB objects.

MIB Object	Description
applIndex	Unique integer index that identifies each database server. This value is the sum of the following values: <ul style="list-style-type: none">• Informix Enterprise ID * 1,000,000 The Informix Enterprise ID is 893. Therefore, Enterprise ID * 1,000,000 is 893,000,000.• SERVERNUM * 1000
applName	Name of the database server
applDirectoryName	No OnSNMP support for this MIB object
applVersion	Version of the database server
applUptime	Time when the database server was last initialized This time is the system time according to the master agent. If the database server was last initialized before OnSNMP was last initialized, this value is 0.
applOperStatus	Operating status of the database server: <ul style="list-style-type: none">• up (1)• down (2)• halted (3)• -- (4): OnSNMP does not use this value.• restarting (5)
applLastChange	Time when the database server entered its current state This time is the system time according to the master agent. If the database server was last initialized before OnSNMP was last initialized, this value is 0.
applInboundAssociations	Number of current SQLCONNECT actions
applOutboundAssociations	OnSNMP does not support this MIB object.
applAccumulatedInboundAssociations	Number of SQLCONNECT actions that have occurred so far
applAccumulatedOutboundAssociations	OnSNMP does not support this MIB object.
applLastInboundActivity	Time for the most recent attempt to start or stop a session with a database server This time is the system time according to the master agent.
applLastOutboundActivity	OnSNMP does not support this MIB object.

applRejectedInboundAssociations

Number of times that the database server rejected an input connection due to administrative reasons or resource limitations

applFailedOutboundAssociations

OnSNMP does not support this MIB object.

RDBMS MIB

The RDBMS MIB defines several tables that provide information about managed database servers and their databases.

rdbmsDbInfoTable

The following list summarizes this table:

Contents:	Information about databases
Index:	rdbmsDbIndex
Scope of a row:	One database that does not have an access state of unavailable (The rdbmsRelState value indicates the access state for the database.)

The table has the following MIB objects.

MIB Object	Description
rdbmsDbIndex	See “rdbmsDbTable” on page 3-5.
rdbmsDbInfoProductName	Name of the database product. For example, this value might be Informix.
rdbmsDbInfoVersion	Version number of the database server that created or last restructured this database
rdbmsDbInfoSizeUnits	Units for rdbmsDbInfoSizeAllocated and rdbmsDbInfoSizeUsed : <ul style="list-style-type: none">• Bytes (1)• Kilobytes (2)• Megabytes (3)• Gigabytes (4)• Terabytes (5)
rdbmsDbInfoSizeAllocated	Estimated size allocated for this database in the units that rdbmsDbInfoSizeUnits specifies
rdbmsDbInfoSizeUsed	Estimated size in use for this database in the units that rdbmsDbInfoSizeUnits specifies
rdbmsDbInfoLastBackup	Date and time when the latest backup of the database was performed. If the database has never been backed up, this value is noSuchInstance (SNMPv2) or noSuchName (SNMPv1).

rdbmsDbLimitedResourceTable

OnSNMP does not support this table.

rdbmsDbParamTable

OnSNMP does not support this table.

rdbmsDbTable

The following list summarizes this table:

Contents:	Information about databases
Index:	rdbmsDbIndex
Scope of a row:	One database

The table has the following MIB objects.

MIB Object	Description
rdbmsDbIndex	Unique integer index that identifies a database. This value is the sum of the following values: <ul style="list-style-type: none">• $\text{SERVERNUM} * 1,000,000$ If SERVERNUM is 0, OnSNMP uses 256 instead of 0.• Database number
rdbmsDbPrivateMibOID	OID for the Informix Private MIB: 1.3.6.1.4.1.893
rdbmsDbVendorName	Name of the database vendor: IBM Corporation
rdbmsDbName	Name of the database
rdbmsDbContact	Login name of the person who created the database

rdbmsRelTable

The following list summarizes this table:

Contents:	Information about the relationship between a database and the database server with which it is associated
-----------	---

The table has the following MIB objects.

MIB Object	Description
rdbmsDbIndex	See “rdbmsDbTable” on page 3-5.
applIndex	See “applTable” on page 3-2.
rdbmsRelState	Access state between the database server and the database: <ul style="list-style-type: none">• Other (1): The database server is online, but one of the dbspaces of the database is down.• Active (2): The database server is actively using the database. The database server is online, and a user opened the database.• Available (3): The database server could use the database if asked to do so. The database server is online, but the database is not open.• Restricted (4): The database is not completely available. The database server is online, and a user opened the database in exclusive mode.

- Unavailable (5)

rdbmsRelActiveTime

Date and time that the database server made the database active. If **rdbmsRelState** is not active, this value is noSuchInstance (SNMPv2) or noSuchName (SNMPv1).

rdbmsSrvInfoTable

The following list summarizes this table:

Contents: Information about the database server since it was started

Index: **applIndex**

Scope of a row: One database server

The table has the following MIB objects.

MIB Object	Description
applIndex	See “applTable” on page 3-2.
rdbmsSrvInfoStartupTime	Date and time when the database server was last started
rdbmsSrvInfoFinishedTransactions	Number of transactions completed, either with a commit or with an abort
rdbmsSrvInfoDiskReads	Number of reads from the physical disk
rdbmsSrvInfoLogicalReads	Number of logical reads
rdbmsSrvInfoDiskWrites	Number of writes to the physical disk
rdbmsSrvInfoLogicalWrites	Number of logical writes
rdbmsSrvInfoPageReads	Number of page reads
rdbmsSrvInfoPageWrites	Number of page writes
rdbmsSrvInfoDiskOutOfSpaces	Number of times that the database server has been unable to obtain the desired disk space
rdbmsSrvInfoHandledRequests	Number of requests made to the database server on inbound associations
rdbmsSrvInfoRequestRecvs	Number of receive operations that the database server made while it was processing requests on inbound associations
rdbmsSrvInfoRequestSends	Number of send operations that the database server made while it was processing requests on inbound associations
rdbmsSrvInfoHighwaterInbound-Associations	Greatest number of inbound associations that have been open at the same time
rdbmsSrvInfoMaxInboundAssociations	Greatest number of inbound associations that can be open at the same time

rdbmsSrvLimitedResourceTable

The following list summarizes this table:

Contents: Information about the limited resources for each database server

Index: **applIndex, rdbmsSrvLimitedResourceName**

Scope of a row: One limited resource

The table has the following MIB objects.

MIB Object	Description
applIndex	See “applTable” on page 3-2.
rdbsmsSrvLimitedResourceName	Name of the limited resource: <ul style="list-style-type: none"> • BUFFERS • DS_MAX_QUERIES • DS_MAX_SCANS • DS_TOTAL_MEMORY • LOCKS • LTXEHW • LTXHWM • STACKSIZE • LOGFILES • DBSPACES • CHUNKS
rdbsmsSrvLimitedResourceID	OID or vendor name for the Informix Private MIB: 1.3.6.1.4.1.893 or informix
rdbsmsSrvLimitedResourceLimit	Maximum value that this limited resource can attain
rdbsmsSrvLimitedResourceCurrent	The current value for this limited resource
rdbsmsSrvLimitedResourceHighwater	Maximum value that this limited resource has attained since applUptime was reset. This value is 0 for DBSPACES and CHUNKS.
rdbsmsSrvLimitedResourceFailures	Number of times that the database server tried to exceed the maximum value for this limited resource since applUptime was reset. This value is 0 for DBSPACES and CHUNKS.
rdbsmsSrvLimitedResourceDescription	Description of the limited resource. This description includes the units for the value for the limited resource.

rdbsmsSrvParamTable

The following list summarizes this table:

Contents:	Information about the configuration parameters for each database server
Index:	applIndex , rdbsmsSrvParamName , rdbsmsSrvParamSubIndex
Scope of a row:	One configuration parameter that is listed in the configuration file for the database server

The **ONCONFIG** environment variable specifies the filename of the configuration file. The following table lists the location of the configuration file for each operating system. For more information about the configuration file, see your *IBM Informix Administrator's Guide* and the *IBM Informix Administrator's Reference*. For more information about the **ONCONFIG** environment variable, see the *IBM Informix Guide to SQL: Reference*.

Operating System	Location of Configuration File
UNIX	\$INFORMIXDIR/etc/\$ONCONFIG
Windows	%INFORMIXDIR%\etc\%ONCONFIG%

The table has the following MIB objects.

MIB Object	Description
applIndex	See “applTable” on page 3-2.
rdbmsSrvParamName	Name of a configuration parameter
rdbmsSrvParamSubindex	Subindex for the configuration parameter. This value is 1 for every configuration parameter except DATASKIP, DBSPACETEMP, DBSERVERALIASES, and NETTYPE.
rdbmsSrvParamID	OID or vendor name for the Informix Private MIB: 1.3.6.1.4.1.893 or informix
rdbmsSrvParamCurrValue	Value of the configuration parameter. OnSNMP obtains this value from the configuration file. Therefore, it does not reflect dynamic changes that you might make to the configuration parameter.
rdbmsSrvParamComment	Purpose of the configuration parameter

rdbmsSrvTable

The following list summarizes this table:

Contents:	Information about a database server
Index:	applIndex
Scope of a row:	One database server

The table has the following MIB objects.

MIB Object	Description
applIndex	See “applTable” on page 3-2.
rdbmsSrvPrivateMibOID	OID for the Informix Private MIB: 1.3.6.1.4.1.893
rdbmsSrvVendorName	Name of the database server vendor: IBM Corporation
rdbmsSrvProductName	Name of the database server product. For example, this value might be Informix.
rdbmsSrvContact	Name of the database server contact: informix

rdbmsTraps

This MIB object contains information about traps that an SNMP subsystem that supports the RDBMS MIB can generate. In this case, the SNMP subsystem is OnSNMP.

frdbmsStateChange trap

When a database server changes from its current status to any less-available status, OnSNMP sends a **rdbmsStateChange** trap message to configured network hosts through the master agent.

The following list summarizes this trap:

Contents:	The rdbmsRelState MIB object
Index:	rdbmsDbIndex , applIndex

Scope of a row:	If the status of an Informix database server becomes unavailable, it generates one trap for each database.
-----------------	--

Online MIB in the Informix private MIB

The Online MIB defines several tables that provide information that is specifically relevant for Informix database servers and their databases.

onActiveBarTable

The following list summarizes this table:

Contents:	Information about the current ON-Bar activity
Index:	applIndex, onActiveBarIndex
Scope of a row:	One ON-Bar activity

The table has the following MIB objects.

MIB Object	Description
applIndex	See “applTable” on page 3-2.
onActiveBarIndex	A number that OnSNMP assigns
onActiveBarActivityType	Type of activity: dbspaceBackup (1) dbspaceRestore (2) logBackup (3) logRestore (4) systemBackup (5) systemRestore (6)
onActiveBarActivityLevel	Level of activity: completeBackup (1) incrementalLevelOne (2) incrementalLevelTwo (3)
onActiveBarElapsedTime	Length of time since the activity started, in hundredths of seconds
onActiveBarActivitySize	Total number of used pages to scan OnSNMP updates this value as the activity progresses.
onActiveBarActivityScanned	Number of used pages that the activity has scanned so far
onActiveBarActivityCompleted	Number of scanned pages that the activity has transferred for archiving so far
onActiveBarActivityStatus	Status of the activity

onActiveTableTable

The following list summarizes this table:

Contents:	Information about the open and active database tables
Index:	applIndex, rdbmsDbIndex, onTableIndex
Scope of a row:	One open and active database table

For a fragmented database table, the values in this table are summaries of the values from all the fragments of the database table. The table has the following MIB objects.

MIB Object	Description
applIndex	See “applTable” on page 3-2.
rdbmsDbIndex	See “rdbmsDbTable” on page 3-5.
onTableIndex	See “onDbospaceTable” on page 3-13.

MIB Object	Description
onActiveTableStatus	Status of the table: <ul style="list-style-type: none"> • not Busy (1): The table is not in use. • busy (2): The table is in use. • dirty (3): The table has been modified.
onActiveTableIsBeingAltered	State of the table: <ul style="list-style-type: none"> • Yes (1): The table is being altered. (An index is being added or dropped, an ALTER TABLE statement is being executed, the alter page count is being updated, or pages are being altered to conform to the latest schema.) • No (2): The table is not being altered.
onActiveTableUsers	Number of users accessing the table
onActiveTableLockRequests	Number of lock requests
onActiveTableLockWaits	Number of lock waits
onActiveTableLockTimeouts	Number of lock timeouts
onActiveTableIsamReads	Number of reads from the database table
onActiveTableIsamWrites	Number of writes to the database table
onActiveTableBufferReads	Number of buffer reads
onActiveTableBufferWrites	Number of buffer writes

onBarTable

The following list summarizes this table:

Contents:	Information about the backup and restore history
Index:	applIndex , onBarActivityIndex , onBarObjectIndex
Scope of a row:	One object that participated in a backup or restore activity

For information about backup and restore, see the *IBM Informix Backup and Restore Guide*. The table has the following MIB objects.

MIB Object	Description
applIndex	See “applTable” on page 3-2.
onBarActivityIndex	Index to the history
onBarObjectIndex	Index to the object
onBarName	Name of the object
onBarType	Type of object: <ul style="list-style-type: none"> • blobSpace (1) (Only Informix provides blobSpaces.) • rootDbSpace (2) • criticalDbSpace (3) • noncriticalDbSpace (4) • logicalLog (5)
onBarLevel	Level of the backup action: <ul style="list-style-type: none"> • completeBackup (1) • incrementalLevelOne(2)

onBarStatus	<ul style="list-style-type: none"> • incrementalLevelTwo (3) Status of the action on the object: <ul style="list-style-type: none"> • 0 = successful • Nonzero = error number
onBarTimeStamp	Ending time stamp for the action

onChunkTable

The following list summarizes this table:

Contents:	Information about the chunks that the database servers use
Index:	applIndex , onDbospaceIndex , onChunkIndex
Scope of a row:	One chunk

The table has the following MIB objects.

MIB Object	Description
applIndex	See “applTable” on page 3-2.
onDbospaceIndex	See “rdbmsDbInfoTable” on page 3-4.
onChunkIndex	Unique integer index for this chunk The database server generates this value.
onChunkFileName	Pathname for the chunk
onChunkFileOffset	Offset into the device, in pages
onChunkPagesAllocated	Chunk size, in pages
onChunkPagesUsed	Number of pages used
onChunkType	Type of chunk: <ul style="list-style-type: none"> • regularChunk (1) • blobChunk (2) • stageBlob (3)
onChunkStatus	Status of the chunk: <ul style="list-style-type: none"> • offline (1) • online (2) • recovering (3) • inconsistent (4) • dropped (5)
onChunkMirroring	Mirroring status of the chunk: <ul style="list-style-type: none"> • notMirrored (1) • mirrored (2) • newlyMirrored (3)
onChunkReads	Number of physical-read operations
onChunkPageReads	Number of page reads
onChunkWrites	Number of physical-write operations
onChunkPageWrites	Number of page writes

onChunkMirrorFileName	Pathname of the mirror chunk If the chunk is not mirrored, this value is noSuchInstance (SNMPv2) or noSuchName (SNMPv1).
onChunkMirrorFileOffset	Offset of the mirror, in pages If the chunk is not mirrored, this value is noSuchInstance (SNMPv2) or noSuchName (SNMPv1).
onChunkMirrorStatus	Mirroring status: <ul style="list-style-type: none"> • offline (1) • online (2) • recovering (3) • inconsistent (4) • dropped (5)

If the chunk is not mirrored, this value is noSuchInstance (SNMPv2) or noSuchName (SNMPv1).

onDatabaseTable

The following list summarizes this table:

Contents:	Information about active databases
Index:	applIndex, rdbmsDbIndex
Scope of a row:	One active database This table does not provide information about an active database if one of the dbspaces for the database is down. (The rdbmsRelState MIB object for each database in rdbmsRelTable indicates whether or not a database is active and whether or not one of its dbspaces is down.)

The table has the following MIB objects.

MIB Object	Description
applIndex	See “applTable” on page 3-2.
rdbmsDbIndex	See “rdbmsDbTable” on page 3-5.
onDatabaseDbspace	Default dbspace
onDatabaseCreated	Creation date and time
onDatabaseLogging	Logging status: <ul style="list-style-type: none"> • none (1) • buffered (2) • unbuffered (3) • ansi (4)
onDatabaseOpenStatus	Database status: <ul style="list-style-type: none"> • notOpen (1) • open (2) • openExclusive (3)

onDatabaseUsers	Number of users
------------------------	-----------------

onDbospaceTable

The following list summarizes this table:

Contents:	Information about dbspaces
Index:	applIndex, onDbospaceIndex
Scope of a row:	One dbspace

The table has the following MIB objects.

MIB Object	Description
applIndex	See “applTable” on page 3-2.
onDbospaceIndex	Unique integer index for this dbspace. The database server generates this value.
onDbospaceName	Name of the dbspace
onDbospaceOwner	Login name of the owner
onDbospaceCreated	Creation date
onDbospaceChunks	Number of chunks in the dbspace
onDbospaceType	Type of dbspace: <ul style="list-style-type: none"> • regularDbospace (1) • temporaryDbospace (2) • blobDbospace (3)
onDbospaceMirrorStatus	Mirroring status: <ul style="list-style-type: none"> • notMirrored (1) • mirrored (2) • mirrorDisabled (3) • newlyMirrored (4)
onDbospaceRecoveryStatus	Recovery status: <ul style="list-style-type: none"> • noRecoveryNeeded (1) • doneRecovery (2) • physicallyRecovered (3) • logicallyRecovering (4)
onDbospaceBackupStatus	Backup status: <ul style="list-style-type: none"> • yes (1): The dbspace is backed up. • no (2): The dbspace is not backed up.
onDbospaceMiscStatus	Miscellaneous status: <ul style="list-style-type: none"> • none (1): no more information • aTableDropped (2)
onDbospacePagesAllocated	Size of all the primary chunks in the dbspace
onDbospacePagesUsed	Number of pages used in all the primary chunks in the dbspace
onDbospaceBackupDate	Date when the latest backup was performed. If the

dbspace has never been backed up, this value is noSuchInstance (SNMPv2) or noSuchName (SNMPv1).

onDbSpaceLastBackupLevel

Level of the last backup. If the dbspace has never been backed up, this value is noSuchInstance (SNMPv2) or noSuchName (SNMPv1).

onDbSpaceLastFullBackupDate

Date and time of the last full backup (level 0). If the dbspace has never had a full backup, this value is noSuchInstance (SNMPv2) or noSuchName (SNMPv1).

onErQueueTable

The following list summarizes this table:

Contents:	Information about the replication queues for all database servers that participate in Enterprise Replication
Index:	applIndex, onErQueueReplIndex
Scope of a row:	One replication queue

The table has the following MIB objects.

MIB Object	Description
applIndex	See “applTable” on page 3-2.
onErQueueReplIndex	Unique integer index that identifies a replicant
onErQueueSiteIndex	Unique integer that identifies a database server
onErQueueReplName	Display string that describes the replicant or collection of replicants
onErQueueSiteName	Name of the Enterprise Replication database server
onErQueueSize	Current number of bytes in the send queue
onErQueueLastCommit	Date and time when last transaction was committed
onErQueueLastAck	Date and time when last data was acknowledged

onErSiteTable

The following list summarizes this table:

Contents:	Information about all the remote database servers that participate in Enterprise Replication
Index:	applIndex, onErSiteIndex
Scope of a row:	A single replication queue

The table has the following MIB objects.

MIB Object	Description
applIndex	See “applTable” on page 3-2.

onErSiteIndex	Integer that uniquely identifies a database server as defined in the group entry in sqlhosts
onErSiteName	Name of the replication site
onErSiteState	State of the replication activity for this site: <ul style="list-style-type: none"> • inactive (1) • active (2) • suspend (3) • quiescent (4) • hold (5) • delete (6) • failed (7) • unknown (8)
onErSiteConnectionState	State of the connection to this site: <ul style="list-style-type: none"> • idle (1) • connected (2) • disconnected (3) • timeout (4) • shutdown (5) • error (6) • unknown (7)
onErSiteConnectionChange	Date and time when the connection state last changed
onErSiteIdleTimeout	Time limit for Enterprise Replication to wait for new data to send or receive. Value is set when database server is defined. Connection is closed if time limit is exceeded.
onErSiteOutMsgs	Total number of messages transmitted from the current database server to this site
onErSiteOutBytes	Total number of bytes transmitted from the current database server to this site
onErSiteInMsgs	Total number of messages received by the current database server from this site
onErSiteInBytes	Total number of bytes received by the current database server from this site
onErSiteTransactions	Total number of transactions received from this site
onErSiteCommits	Total number of transactions received and committed from this site
onErSiteAborts	Total number of transactions aborted from this site
onErSiteLastReceived	Date and time when the last transaction was processed from this site
onErSiteRowCommits	Total number of rows committed from this site
onErSiteRowAborts	Total number of rows aborted from this site

onErSiteRcvLatency	Average latency between the source commit time and target receive time; performance measure of network queueing delay
onErSiteCommitLatency	Average latency between source and target commit time; performance measure of network and database server delay
onErSiteClockErrors	Number of transactions received from this site with a time that is ahead of our current time; indicates system clock synchronization problems

onFragmentTable

The following list summarizes this table:

Contents:	Information about the fragments that are in fragmented database tables
Index:	applIndex, rdbmsDbIndex, onTableIndex, onFragmentIndex
Scope of a row:	One fragment of a fragmented database table

The table has the following MIB objects.

MIB Object	Description
applIndex	See “applTable” on page 3-2.
rdbmsDbIndex	See “rdbmsDbTable” on page 3-5.
onTableIndex	See “onDbospaceTable” on page 3-13.
onFragmentIndex	Unique integer index for the fragment
onFragmentType	Type of database table: <ul style="list-style-type: none"> • fragmentedIndex (1) • fragmentedTable (2)
onFragmentDbospace	Dbospace name for the fragment
onFragmentExpression	Expression text used for fragmentation of the table or index <p>This value is blank if the fragmentation scheme is round-robin.</p>
onFragmentIndexName	Index identifier
onFragmentExtents	Number of extents used
onFragmentPagesAllocated	Total (extent) size allocated to the fragment, in pages
onFragmentPagesUsed	Number of pages used
onFragmentIsamReads	Number of reads from the fragment <p>If the fragment is not active, this value is noSuchInstance (SNMPv2) or noSuchName (SNMPv1).</p>
onFragmentIsamWrites	Number of writes to the fragment

	If the fragment is not active, this value is noSuchInstance (SNMPv2) or noSuchName (SNMPv1).
onFragmentUsers	Number of user threads that access the fragment.
onFragmentLockRequests	Number of locks of any type requested for this fragment.
onFragmentLockWaits	Number of times an initial lock request failed because the lock could not be granted initially for the fragment.
onFragmentLockTimeouts	Number of deadlock timeouts for the fragment.

onLockTable

The following list summarizes this table:

Contents:	Information about the active locks that database servers are using
Index:	applIndex, onSessionIndex, onLockIndex
Scope of a row:	One lock A row exists for each lock that the session is using and for each lock on which the session is waiting.

The table has the following MIB objects.

MIB Object	Description
applIndex	See “applTable” on page 3-2.
onSessionIndex	See “onServerTable” on page 3-19.
onLockIndex	Index to this row
onLockDatabaseName	Name of the database that is using or waiting for this lock
onLockTableName	Name of the table that is using or waiting for this lock
onLockType	Type of the lock: <ul style="list-style-type: none"> • byte (1) • intentShared (2) • shared (3) • sharedByRepeatableRead (4) • update (5) • intentExclusive (6) • sharedIntentExclusive (7) • exclusive (8) • exclusiveByRepeatableRead (9) • waiting (10)
onLockGranularity	Granularity of the lock: <ul style="list-style-type: none"> • table (1) • page (2) • row (3)

	<ul style="list-style-type: none"> • index (4)
onLockRowId	rowid of the locked row
onLockWaiters	Number of sessions that are waiting for the lock
onLockGrantTime	Time when the lock was granted if the session is using the lock
	If no transaction exists, this value is noSuchInstance (SNMPv2) or noSuchName (SNMPv1).

onLogicalLogTable

The following list summarizes this table:

Contents:	Information about logical logs
Index:	applIndex, onLogicalLogIndex
Scope of a row:	One logical log

The table has the following MIB objects.

MIB Object	Description
applIndex	See “applTable” on page 3-2.
onLogicalLogIndex	Index for the logical-log file
onLogicalLogID	Unique integer identification number for the logical-log file
onLogicalLogDbSpace	DbSpace name where the log file was created
onLogicalLogStatus	Status of the logical-log file: <ul style="list-style-type: none"> • newlyAdded (1) • free (2) • current (3) • used (4) • backedUpButNeeded (5)
onLogicalLogContainsLastCheckpoint	Checkpoint status: <ul style="list-style-type: none"> • yes (1): The logical-log file contains the last checkpoint. • no (2): The logical-log file does not contain the last checkpoint.
onLogicalLogIsTemporary	Temporary status: <ul style="list-style-type: none"> • yes (1): The logical-log file is temporary. • no (2): The logical-log file is not temporary.
onLogicalLogPagesAllocated	Size of the logical-log file, in pages
onLogicalLogPagesUsed	Number of pages used in the logical-log file
onLogicalLogFillTime	Date and time when the logical-log file last filled up If the log file has never been full, this value is noSuchInstance (SNMPv2) or noSuchName (SNMPv1).
onLogicalLogTimeUniqueIDChanged	Time stamp when a new unique ID was assigned to this logical-log entry
onLogicalLogTimeLastBackupDate	Date and time of the last backup for this logical-log entry

onPhysicalLogTable

The following list summarizes this table:

Contents:	Information about physical logs
Index:	applIndex
Scope of a row:	One physical log

The table has the following MIB objects.

MIB Object	Description
applIndex	See “applTable” on page 3-2.
onPhysicalLogDbSpace	DbSpace name where the physical log was created
onPhysicalLogBufferSize	Size of the physical-log buffer, in pages
onPhysicalLogBufferUsed	Number of pages of the physical-log buffer that are used
onPhysicalLogPageWrites	Number of pages written to the physical log
onPhysicalLogWrites	Number of (disk) writes to the physical log
onPhysicalLogPagesAllocated	Size of the physical log, in pages
onPhysicalLogPagesUsed	Number of pages used

onServerTable

The following list summarizes this table:

Contents:	Status and profile information about each active database server
Index:	applIndex
Scope of a row:	One database server

The table has the following MIB objects.

MIB Object	Description
applIndex	See “applTable” on page 3-2
onServerMode	Mode of the database server: <ul style="list-style-type: none"> • initializing (1) • quiescent (2) • fastRecovery (3) • backingUp (4) • shuttingDown (5) • online (6) • aborting (7) • onlineReadOnly (8)
onServerCheckpointInProgress	Checkpoint status: <ul style="list-style-type: none"> • yes (1): A checkpoint is in progress. • no (2): A checkpoint is not in progress.
onServerPageSize	Size of a page, in bytes
onServerThreads	Number of active threads
onServerVPs	Number of virtual processors
onServerVirtualMemory	Total virtual memory used, in kilobytes

MIB Object	Description
onServerResidentMemory	Total resident memory used, in kilobytes
onServerMessageMemory	Total message memory used, in kilobytes
onServerIsamCalls	Sum of all reads, writes, rewrites, deletes, commits, and rollbacks to and from the database table
onServerLatchWaits	Number of latch waits
onServerLockRequests	Number of lock requests
onServerLockWaits	Number of lock waits
onServerBufferWaits	Number of buffer waits
onServerCheckpointWaits	Number of checkpoint waits
onServerDeadLocks	Number of deadlocks
onServerLockTimeouts	Number of deadlock time-outs
onServerLogicalLogRecords	Number of logical-log records
onServerLogicalLogPageWrites	Number of logical-log page writes
onServerLogicalLogWrites	Number of logical-log writes
onServerBufferFlushes	Number of buffer flushes
onServerForegroundWrites	Number of foreground writes
onServerLRUWrites	Number of LRU writes
onServerChunkWrites	Number of chunk writes
onServerReadAheadPages	Number of read-ahead pages This value includes data and index read-ahead pages.
onServerReadAheadPagesUsed	Number of read-ahead pages used
onServerSequentialScans	Number of sequential scans
onServerMemorySorts	Number of memory sorts
onServerDiskSorts	Number of disk sorts
onServerMaxSortSpace	Maximum disk space that a sort uses, in pages
onServerNetworkReads	Number of network reads
onServerNetworkWrites	Number of network writes
onServerPDQCalls	Number of parallel-processing actions performed
onServerTransactionCommits	Number of committed transactions
onServerTransactionRollbacks	Number of rolled-back transactions
onServerTimeSinceLastCheckpoint	Length of time since the last checkpoint, in hundredths of second
onServerCPUSystemTime	Amount of CPU time that the database server has used in System Mode, in hundredths of second
onServerCPUUserTime	Amount of CPU time that the database server has used in User Mode, in hundredths of second

onSessionTable

The following list summarizes this table:

Contents:	Information about each session
Index:	applIndex, onSessionIndex
Scope of a row:	One session

The table has the following MIB objects.

MIB Object	Description
applIndex	See “applTable” on page 3-2.
onSessionIndex	Unique integer index for the session
onSessionUserName	Name of the user, in the form name@host(tty)
onSessionUserProgramVersion	Version of the database server
onSessionUserProcessId	Process ID for the session
onSessionUserTime	Length of time that the user has been connected to the database server, in hundredths of seconds
onSessionState	State of the session: <ul style="list-style-type: none"> • idle (1) • active (2) • waitingOnMutex (3) • waitingOnCondition (4) • waitingOnLock (5) • waitingOnBuffer (6) • waitingOnCheckPointing (7) • waitingOnLogicalLogWrite (8) • waitingOnTransaction (9)
onSessionDatabase	Connected database
onSessionCurrentMemory	Memory usage, in bytes
onSessionThreads	Number of active threads
onSessionCurrentStack	Average size of the stack for all threads
onSessionHighwaterStack	Maximum amount of memory that any thread has used so far
onSessionLockRequests	Number of lock requests
onSessionLocksHeld	Number of locks held
onSessionLockWaits	Number of lock waits
onSessionLockTimeouts	Number of time-outs for locks
onSessionLogRecords	Number of log records
onSessionIsamReads	Number of reads from database tables
onSessionIsamWrites	Number of writes to database tables
onSessionPageReads	Number of page reads
onSessionPageWrites	Number of page writes
onSessionLongTxs	Number of long transactions
onSessionLogSpace	Logical-log space used, in bytes
onSessionHighwaterLogSpace	Maximum logical-log space that this session has ever used
onSessionSqlStatement	Latest SQL statement, truncated to 250 characters if necessary
onSessionSqlIsolation	SQL isolation level: <ul style="list-style-type: none"> • noTransactions (1) • dirtyReads (2) • readCommitted (3) • cursorRecordLocked (4) • repeatableRead (5)

MIB Object	Description
onSessionSqlLockWaitMode	Action to take if the isolation level requires a wait: <ul style="list-style-type: none"> • -1 = Wait forever. • 0 = Do not wait. • >0 = Wait for specified number of seconds.
onSessionSqlEstimatedCost	Estimated cost of the SQL statement according to SQLEXPLAIN
onSessionSqlEstimatedRows	Estimated number of rows that the SQL statement will select according to SET EXPLAIN
onSessionSqlError	Error number for the last SQL statement
onSessionSqlIsamError	ISAM error number for the last SQL statement
onSessionTransactionStatus	Status of the transaction: <ul style="list-style-type: none"> • none (1) • committing (2) • rollingBack (3) • rollingHeuristically (4) • waiting (5)
onSessionTransactionBeginLog	Unique ID of the logical-log file in which the BEGIN WORK record was logged If no transaction exists, this value is noSuchInstance (SNMPv2) or noSuchName (SNMPv1).
onSessionTransactionLastLog	Unique ID of the logical-log file in which the last record was logged If no transaction exists, this value is noSuchInstance (SNMPv2) or noSuchName (SNMPv1).
onSessionOriginatingSessionId	Local session ID of the global session on the server for which this local session runs

onSqlHostTable

The following list summarizes this table:

Contents:	Copy of the connection information
Index:	applIndex, onSqlHostIndex
Scope of a row:	One connectivity value

As the following table shows, the location of the connection information depends on the operating system. For details about the connection information, see your *IBM Informix Administrator's Guide*.

Operating System	Location of Connectivity Information
UNIX	The INFORMIXSQLHOSTS environment variable specifies the full pathname and filename of the connection information. The default location is \$INFORMIXDIR/etc/sqlhosts . For information about INFORMIXSQLHOSTS , see the <i>IBM Informix Guide to SQL: Reference</i> .
Windows	The connectivity information is in a key in the Windows registry called HKEY_LOCAL_MACHINE\SOFTWARE\Informix\SQLHOSTS .

The table has the following MIB objects.

MIB Object	Description
applIndex	See “applTable” on page 3-2.
onSqlHostIndex	Index to the entry in the connectivity information
onSqlHostName	Host name of the database server
onSqlHostNetType	Connection type
onSqlHostServerName	Name of the database server or its alias
onSqlHostServiceName	Service name
onSqlHostOptions	List server options in the form of key=value pairs

onTableTable

The following list summarizes this table:

Contents:	Information about a database table
Index:	applIndex , rdBmsDbIndex , onTableIndex
Scope of a row:	One database table

For a fragmented database table, the values in this table are summaries of the values from all the database table fragments. The table has the following MIB objects.

MIB Object	Description
applIndex	See “applTable” on page 3-2.
rdBmsDbIndex	See “rdBmsDbTable” on page 3-5.
onTableIndex	Table number This value is the same as tabid in the system catalog table systables
onTableName	Table name
onTableOwner	Table owner
onTableType	Type of table: <ul style="list-style-type: none">• table (1)• view (2)• privateSynonym (3)• synonym (4)
onTableLockLevel	Locking level of the table: <ul style="list-style-type: none">• page (1)• row (2)
onTableCreated	Creation date, in string format
onTableFirstDbSpace	Name of the first (or only) dbspace for the table
onTableRowSize	Length of a row
onTableRows	Number of rows
onTableColumns	Number of columns
onTableIndices	Number of indexes

onTableExtents	Number of extents in use
onTablePagesAllocated	Total (extent) size allocated to the table, in pages
onTablePagesUsed	Number of pages in use
onTableFragments	Number of fragments
onTableFragmentStrategy	Fragmentation strategy: <ul style="list-style-type: none"> • roundRobin (1) • byExpression (2) • tableBased (3)

If the table is not fragmented, this value is noSuchInstance (SNMPv2) or noSuchName (SNMPv1).

onTableActiveFragments	Number of active fragments If the table is not fragmented, this value is noSuchInstance (SNMPv2) or noSuchName (SNMPv1).
-------------------------------	---

Appendix. Accessibility

IBM strives to provide products with usable access for everyone, regardless of age or ability.

Accessibility features for IBM Informix

Accessibility features help a user who has a physical disability, such as restricted mobility or limited vision, to use information technology products successfully.

Accessibility Features

The following list includes the major accessibility features in IBM Informix. These features support:

- Keyboard-only operation.
- Interfaces that are commonly used by screen readers.
- The attachment of alternative input and output devices.

Tip: The IBM Informix Information Center and its related publications are accessibility-enabled for the IBM Home Page Reader. You can operate all features using the keyboard instead of the mouse.

Keyboard Navigation

This product uses standard Microsoft Windows navigation keys.

Related Accessibility Information

IBM is committed to making our documentation accessible to persons with disabilities. Our publications are available in HTML format so that they can be accessed with assistive technology such as screen reader software. The syntax diagrams in our publications are available in dotted decimal format. For more information about the dotted decimal format, go to “Dotted Decimal Syntax Diagrams.”

You can view the publications for IBM Informix in Adobe Portable Document Format (PDF) using the Adobe Acrobat Reader.

IBM and Accessibility

See the *IBM Accessibility Center* at <http://www.ibm.com/able> for more information about the commitment that IBM has to accessibility.

Dotted Decimal Syntax Diagrams

The syntax diagrams in our publications are available in dotted decimal format, which is an accessible format that is available only if you are using a screen reader.

In dotted decimal format, each syntax element is written on a separate line. If two or more syntax elements are always present together (or always absent together), the elements can appear on the same line, because they can be considered as a single compound syntax element.

Each line starts with a dotted decimal number; for example, 3 or 3.1 or 3.1.1. To hear these numbers correctly, make sure that your screen reader is set to read punctuation. All syntax elements that have the same dotted decimal number (for example, all syntax elements that have the number 3.1) are mutually exclusive alternatives. If you hear the lines 3.1 USERID and 3.1 SYSTEMID, your syntax can include either USERID or SYSTEMID, but not both.

The dotted decimal numbering level denotes the level of nesting. For example, if a syntax element with dotted decimal number 3 is followed by a series of syntax elements with dotted decimal number 3.1, all the syntax elements numbered 3.1 are subordinate to the syntax element numbered 3.

Certain words and symbols are used next to the dotted decimal numbers to add information about the syntax elements. Occasionally, these words and symbols might occur at the beginning of the element itself. For ease of identification, if the word or symbol is a part of the syntax element, the word or symbol is preceded by the backslash (\) character. The * symbol can be used next to a dotted decimal number to indicate that the syntax element repeats. For example, syntax element *FILE with dotted decimal number 3 is read as 3 * FILE. Format 3* FILE indicates that syntax element FILE repeats. Format 3* * FILE indicates that syntax element * FILE repeats.

Characters such as commas, which are used to separate a string of syntax elements, are shown in the syntax just before the items they separate. These characters can appear on the same line as each item, or on a separate line with the same dotted decimal number as the relevant items. The line can also show another symbol that provides information about the syntax elements. For example, the lines 5.1*, 5.1 LASTRUN, and 5.1 DELETE mean that if you use more than one of the LASTRUN and DELETE syntax elements, the elements must be separated by a comma. If no separator is given, assume that you use a blank to separate each syntax element.

If a syntax element is preceded by the % symbol, that element is defined elsewhere. The string following the % symbol is the name of a syntax fragment rather than a literal. For example, the line 2.1 %OP1 means that you should refer to a separate syntax fragment OP1.

The following words and symbols are used next to the dotted decimal numbers:

- ? Specifies an optional syntax element. A dotted decimal number followed by the ? symbol indicates that all the syntax elements with a corresponding dotted decimal number, and any subordinate syntax elements, are optional. If there is only one syntax element with a dotted decimal number, the ? symbol is displayed on the same line as the syntax element (for example, 5? NOTIFY). If there is more than one syntax element with a dotted decimal number, the ? symbol is displayed on a line by itself, followed by the syntax elements that are optional. For example, if you hear the lines 5 ?, 5 NOTIFY, and 5 UPDATE, you know that syntax elements NOTIFY and UPDATE are optional; that is, you can choose one or none of them. The ? symbol is equivalent to a bypass line in a railroad diagram.
- ! Specifies a default syntax element. A dotted decimal number followed by the ! symbol and a syntax element indicates that the syntax element is the default option for all syntax elements that share the same dotted decimal number. Only one of the syntax elements that share the same dotted decimal number can specify a ! symbol. For example, if you hear the lines

2? FILE, 2.1! (KEEP), and 2.1 (DELETE), you know that (KEEP) is the default option for the FILE keyword. In this example, if you include the FILE keyword but do not specify an option, default option KEEP is applied. A default option also applies to the next higher dotted decimal number. In this example, if the FILE keyword is omitted, default FILE(KEEP) is used. However, if you hear the lines 2? FILE, 2.1, 2.1.1! (KEEP), and 2.1.1 (DELETE), the default option KEEP only applies to the next higher dotted decimal number, 2.1 (which does not have an associated keyword), and does not apply to 2? FILE. Nothing is used if the keyword FILE is omitted.

- * Specifies a syntax element that can be repeated zero or more times. A dotted decimal number followed by the * symbol indicates that this syntax element can be used zero or more times; that is, it is optional and can be repeated. For example, if you hear the line 5.1* data-area, you know that you can include more than one data area or you can include none. If you hear the lines 3*, 3 HOST, and 3 STATE, you know that you can include HOST, STATE, both together, or nothing.

Notes:

1. If a dotted decimal number has an asterisk (*) next to it and there is only one item with that dotted decimal number, you can repeat that same item more than once.
 2. If a dotted decimal number has an asterisk next to it and several items have that dotted decimal number, you can use more than one item from the list, but you cannot use the items more than once each. In the previous example, you could write HOST STATE, but you could not write HOST HOST.
 3. The * symbol is equivalent to a loop-back line in a railroad syntax diagram.
- + Specifies a syntax element that must be included one or more times. A dotted decimal number followed by the + symbol indicates that this syntax element must be included one or more times. For example, if you hear the line 6.1+ data-area, you must include at least one data area. If you hear the lines 2+, 2 HOST, and 2 STATE, you know that you must include HOST, STATE, or both. As for the * symbol, you can only repeat a particular item if it is the only item with that dotted decimal number. The + symbol, like the * symbol, is equivalent to a loop-back line in a railroad syntax diagram.

Notices

This information was developed for products and services offered in the U.S.A.

IBM may not offer the products, services, or features discussed in this document in all countries. Consult your local IBM representative for information on the products and services currently available in your area. Any reference to an IBM product, program, or service is not intended to state or imply that only that IBM product, program, or service may be used. Any functionally equivalent product, program, or service that does not infringe any IBM intellectual property right may be used instead. However, it is the user's responsibility to evaluate and verify the operation of any non-IBM product, program, or service.

IBM may have patents or pending patent applications covering subject matter described in this document. The furnishing of this document does not give you any license to these patents. You can send license inquiries, in writing, to:

IBM Director of Licensing
IBM Corporation
North Castle Drive
Armonk, NY 10504-1785
U.S.A.

For license inquiries regarding double-byte (DBCS) information, contact the IBM Intellectual Property Department in your country or send inquiries, in writing, to:

Intellectual Property Licensing
Legal and Intellectual Property Law
IBM Japan Ltd.
1623-14, Shimotsuruma, Yamato-shi
Kanagawa 242-8502 Japan

The following paragraph does not apply to the United Kingdom or any other country where such provisions are inconsistent with local law:

INTERNATIONAL BUSINESS MACHINES CORPORATION PROVIDES THIS PUBLICATION "AS IS" WITHOUT WARRANTY OF ANY KIND, EITHER EXPRESS OR IMPLIED, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF NON-INFRINGEMENT, MERCHANTABILITY OR FITNESS FOR A PARTICULAR PURPOSE. Some states do not allow disclaimer of express or implied warranties in certain transactions, therefore, this statement may not apply to you.

This information could include technical inaccuracies or typographical errors. Changes are periodically made to the information herein; these changes will be incorporated in new editions of the publication. IBM may make improvements and/or changes in the product(s) and/or the program(s) described in this publication at any time without notice.

Any references in this information to non-IBM Web sites are provided for convenience only and do not in any manner serve as an endorsement of those Web sites. The materials at those Web sites are not part of the materials for this IBM product and use of those Web sites is at your own risk.

IBM may use or distribute any of the information you supply in any way it believes appropriate without incurring any obligation to you.

Licensees of this program who wish to have information about it for the purpose of enabling: (i) the exchange of information between independently created programs and other programs (including this one) and (ii) the mutual use of the information which has been exchanged, should contact:

IBM Corporation
J46A/G4
555 Bailey Avenue
San Jose, CA 95141-1003
U.S.A.

Such information may be available, subject to appropriate terms and conditions, including in some cases, payment of a fee.

The licensed program described in this information and all licensed material available for it are provided by IBM under terms of the IBM Customer Agreement, IBM International Program License Agreement, or any equivalent agreement between us.

Any performance data contained herein was determined in a controlled environment. Therefore, the results obtained in other operating environments may vary significantly. Some measurements may have been made on development-level systems and there is no guarantee that these measurements will be the same on generally available systems. Furthermore, some measurements may have been estimated through extrapolation. Actual results may vary. Users of this document should verify the applicable data for their specific environment.

Information concerning non-IBM products was obtained from the suppliers of those products, their published announcements or other publicly available sources. IBM has not tested those products and cannot confirm the accuracy of performance, compatibility or any other claims related to non-IBM products. Questions on the capabilities of non-IBM products should be addressed to the suppliers of those products.

All statements regarding IBM's future direction or intent are subject to change or withdrawal without notice, and represent goals and objectives only.

All IBM prices shown are IBM's suggested retail prices, are current and are subject to change without notice. Dealer prices may vary.

This information contains examples of data and reports used in daily business operations. To illustrate them as completely as possible, the examples include the names of individuals, companies, brands, and products. All of these names are fictitious and any similarity to the names and addresses used by an actual business enterprise is entirely coincidental.

COPYRIGHT LICENSE:

This information contains sample application programs in source language, which illustrate programming techniques on various operating platforms. You may copy, modify, and distribute these sample programs in any form without payment to IBM, for the purposes of developing, using, marketing or distributing application programs conforming to the application programming interface for the operating platform for which the sample programs are written. These examples have not

been thoroughly tested under all conditions. IBM, therefore, cannot guarantee or imply reliability, serviceability, or function of these programs. The sample programs are provided "AS IS", without warranty of any kind. IBM shall not be liable for any damages arising out of your use of the sample programs.

Each copy or any portion of these sample programs or any derivative work, must include a copyright notice as follows:

© (your company name) (year). Portions of this code are derived from IBM Corp. Sample Programs. © Copyright IBM Corp. (enter the year or years). All rights reserved.

If you are viewing this information softcopy, the photographs and color illustrations may not appear.

Trademarks

IBM, the IBM logo, and [ibm.com](http://www.ibm.com)[®] are trademarks or registered trademarks of International Business Machines Corp., registered in many jurisdictions worldwide. Other product and service names might be trademarks of IBM or other companies. A current list of IBM trademarks is available on the Web at "Copyright and trademark information" at <http://www.ibm.com/legal/copytrade.shtml>.

Adobe, the Adobe logo, and PostScript are either registered trademarks or trademarks of Adobe Systems Incorporated in the United States, and/or other countries.

Intel, Itanium, and Pentium are trademarks or registered trademarks of Intel Corporation or its subsidiaries in the United States and other countries.

Java and all Java-based trademarks are trademarks of Sun Microsystems, Inc. in the United States, other countries, or both.

Linux is a registered trademark of Linus Torvalds in the United States, other countries, or both.

Microsoft, Windows, and Windows NT are trademarks of Microsoft Corporation in the United States, other countries, or both.

UNIX is a registered trademark of The Open Group in the United States and other countries.

Other company, product, or service names may be trademarks or service marks of others.

Index

A

Abstract Syntax Notation One.
 See ASN.1.
Accessibility A-1
 dotted decimal format of syntax diagrams A-1
 keyboard A-1
 shortcut keys A-1
 syntax diagrams, reading in a screen reader A-1
Application MIB
 location in hierarchy 2-14
 reference 3-2
APPLMIB registry argument 2-12
applTable 3-2
ASN.1, description 1-5

C

Commands
 grep 2-7
 inssnmp 2-14
 onsrvapd 2-10, 2-18
 runsnmp.ksh 2-6
 snmpdm 2-8
Configuration
 EMANATE master agent 2-7
 file location 3-7
 for traps 1-5
 master agent 2-7
 OnSNMP 2-9, 2-12
 parameter files 3-7
Connectionless protocol 1-3

D

Data requests
 example 2-2
 general description 1-5
 Informix implementation 2-2
Database servers
 configuration parameters 3-7
 locks 3-17
Database tables, fragmented 3-16
Databases
 general information 3-4
 sysmaster 2-3
 sysutils 2-3
dbspaces 3-13
Directories
 for MIB files 3-1
 for Windows Subagent 2-11
 SNMP 2-6
Disabilities, visual
 reading syntax diagrams A-1
Disability A-1
Dotted decimal format of syntax diagrams A-1

E

EMANATE master agent 2-7
Enterprise Replication 3-14
Environment variables
 INFORMIXDIR 2-6
 INFORMIXSQLHOSTS 3-22
 ONCONFIG 3-7
 PATH 2-7
 SR_AGT_CONF_DIR 2-7
 SR_LOG_DIR 2-7
Error -23101 2-14
Error messages
 EMANATE log file 2-9
 turning on 2-9
Event notification
 example 2-2
 general description 1-4
 Informix implementation 2-2

F

Files
 EMANATE log 2-9
 infxsnmp.dll 2-11
 installed on UNIX 2-18
 installed on Windows 2-19
 location of configuration 3-7
 MIB directory 3-1
 onsnmp.exe 2-12
 onsrvapd.exe 2-12
 runsnmp.ksh 2-6
Fragmented database tables 3-16

G

Global Language Support (GLS)
 and SNMP 2-14

H

Hierarchy of MIBs.
 See also MIBs
 hierarchy. v

I

IANA.
 See Internet Assigned Numbers Authority.
IETF.
 See Internet Engineering Task Force.
Informix Private MIB, location in hierarchy 2-15
INFXSNMP registry argument 2-12
infxsnmp.dll file, description 2-11
inssnmp program 2-14
Installation
 files for UNIX and Windows 2-18
 master agent on UNIX 2-7
 master agent on Windows 2-11
 required software 2-5, 2-11

Installation (*continued*)
 subagent on UNIX 2-9
 subagent on Windows 2-11
Internet Assigned Numbers Authority 1-5, 2-15
Internet Engineering Task Force 2-14

L

LINGER_TIME registry argument 2-12
Locks 3-17
LOGDIR registry argument 2-12
Logical log 3-18
LOGLEVEL registry argument 2-12
Logs
 logical 3-18
 physical 3-18

M

Managed components
 general description 1-4
 in SNMP architecture 1-1
 Informix implementation 2-2
Management Information Bases.
 See MIBs.
Master agents
 configuring on UNIX 2-7
 EMANATE 2-7
 general description 1-4
 in SNMP architecture 1-1
 Informix implementation
 on UNIX 2-6
 on Windows 2-11
 installing on UNIX 2-7
 starting on UNIX 2-8
 stopping on UNIX 2-8
MIB tables.
 See MIBs.
MIBs
 general description 1-5
 hierarchy 1-5, 2-15
 in SNMP architecture 1-1
 indexing 2-17
 Informix implementation 2-14
 naming conventions 1-5
 reference 3-1
 tables 3-1

N

Network managers.
 See SNMP network managers.

O

Object Identifiers.
 See OIDs.
OIDs
 definition 1-6
 in MIB hierarchy 1-5
onActiveBarTable 3-9
onBarTable 3-10
onChunkTable 3-11
onDatabaseTable 3-12
onDbospaceTable 3-13

onErQueueTable 3-14
onErSiteTable 3-14
onFragmentTable 3-16
Online MIB
 location in hierarchy 2-16
 reference 3-9
onLockTable 3-17
onLogicalLogTable 3-18
ONMIB registry argument 2-12
onPhysicalLogTable 3-18
onServerTable 3-19
onSessionTable 3-20
onsnmp.
 See Subagents.
OnSNMP.
 See Subagents.
onsnmp.exe file, description 2-12
OnSnmpSubagent registry keys 2-12
onSqlHostTable 3-22
onsrvapd
 arguments 2-6, 2-10
 server-discovery daemon 2-6
 starting on UNIX 2-9
 stopping on UNIX 2-9
onsrvapd.exe file, description 2-12
onstat utility 2-3
onTableTable 3-23

P

PATH environment variable 2-7
Pathname registry argument 2-12
Physical log 3-18
Program
 inssnmp 2-14
 master agent 1-4
 onsnmp 2-9
 SNMP network manager 1-2
 subagent 1-4

R

RDBMS MIB
 location in hierarchy 2-15
 reference 3-4
rdbmsDbInfoTable 3-4
rdbmsDbLimitedResourceTable 3-4
rdbmsDbParamTable 3-5
rdbmsDbTable 3-5
RDBMSMIB registry argument 2-12
rdbmsRelTable 3-5
rdbmsSrvInfoTable 3-6
rdbmsSrvLimitedResourceTable 3-6
rdbmsSrvParamTable 3-7
rdbmsSrvTable 3-8
rdbmsTraps 3-8
REFRESH_TIME registry argument 2-12
Registry arguments
 APPLMIB 2-12
 INFXSNMP 2-12
 LINGER_TIME 2-12
 LOGDIR 2-12
 LOGLEVEL 2-12
 ONMIB 2-12
 Pathname 2-12
 RDBMSMIB 2-12

Registry arguments (*continued*)
 REFRESH_TIME 2-12
Registry keys, OnSnmpSubagent 2-12
runsnmp.ksh script 2-6

S

Screen reader
 reading syntax diagrams A-1
Script, runsnmp.ksh 2-6
Server discovery process
 See also onsrvapd.
 definition of 2-5
Shortcut keys
 keyboard A-1
SMI.
 See Structure of Management Information.
SNMP
 general description 1-1
 purpose 1-1, 2-2
 versions 2-3
SNMP architecture
 general description 1-1
 Informix implementation on UNIX 2-4
 Informix implementation on Windows 2-4
SNMP network managers
 examples 1-3
 general description 1-2
 in SNMP architecture 1-1
 vendors 1-2
SR_AGT_CONF_DIR environment variable 2-7
SR_LOG_DIR environment variable 2-7
Structure of Management Information 1-5
Subagents
 configuring on Windows 2-12
 general description 1-4
 in SNMP architecture 1-1
 information provided by OnSNMP 2-3
 Informix implementation
 on UNIX 2-9
 on Windows 2-11
 installing
 on UNIX 2-9
 on Windows 2-11
 starting
 on UNIX 2-9
 on Windows 2-11
 stopping
 on UNIX 2-9
 on Windows 2-11
Syntax
 onsrvapd 2-10
 runsnmp.ksh 2-6
Syntax diagrams
 reading in a screen reader A-1

T

Table
 MIB, event column 2-2
 MIB, naming 1-5
 system catalog 2-3
Table, application MIB applTable 3-2
Table, Online MIB
 onActiveBarTable 3-9
 onActiveTableTable 3-9

Table, Online MIB (*continued*)
 onBarTable 3-10
 onChunkTable 3-11
 onDatabaseTable 3-12
 onDbSpaceTable 3-13
 onErQueueTable 3-14
 onErSiteTable 3-14
 onFragmentTable 3-16
 onLockTable 3-17
 onLogicalLogTable 3-18
 onPhysicalLogTable 3-18
 onServerTable 3-19
 onSessionTable 3-20
 onSqlHostTable 3-22
 onTableTable 3-23
Table, RDBMS MIB
 rdbmsDbInfoTable 3-4
 rdbmsDbTable 3-5
 rdbmsRelTable 3-5
 rdbmsSrvInfoTable 3-6
 rdbmsSrvLimitedResourceTable 3-6
 rdbmsSrvParamTable 3-7
 rdbmsSrvTable 3-8
Traps
 example 2-3
 general description 1-5
 Informix implementation 2-3

U

Utilities, onstat 2-3

V

Visual disabilities
 reading syntax diagrams A-1



Printed in USA

SC27-3812-00

